

ORBit Beginners Documentation V1.6

Ewan Birney

Michael Lausch

Todd Lewis

Stéphane Genaud

Frank Rehberger

ORBit Beginners Documentation V1.6

by Ewan Birney, Michael Lausch, Todd Lewis, Stéphane Genaud, and Frank Rehberger

Published 2003

Table of Contents

1. Introduction.....	1
1.1. About this documentation	1
1.1.1. Change Notes between 1.5 and 1.4.....	2
1.1.2. Change Notes between 1.4 and 1.3.....	2
1.1.3. Change Notes between 1.3 and 1.2.....	2
1.1.4. Change Notes between 1.2 and 1.1.....	2
2. Frequently Asked Questions	4
2.1. General Questions	4
2.1.1. What is CORBA?.....	4
2.1.2. What is ORBit?.....	4
2.1.3. Why aren't you using ILU/MICO/TAO?.....	4
2.1.4. Is ORBit stable?.....	4
2.1.5. Does ORBit work with other ORBs?.....	4
2.1.6. What license does ORBit get distributed with and how does it affect me?.....	5
2.1.7. Why doesn't ORBit compile with my cc compiler ?.....	5
2.1.8. What is a language binding?.....	5
2.1.9. What language bindings does ORBit provide?.....	5
2.1.10. Does ORBit have DII and DS?.....	5
2.1.11. Does ORBit provide a naming service?.....	5
2.1.12. Can you encrypt a CORBA connection?.....	6
2.2. Common Coding Problems	6
2.2.1. LD_LIBRARY_PATH not defined	6
2.2.2. IOR strings with newlines.....	6
2.2.3. Activating POAManager before servants can handle requests	6
3. Installing ORBit	7
3.1. Installing from RPMS	7
3.2. Installing from Source.....	7
3.3. Getting the examples to run.....	7
3.4. Known platforms where ORBit works	8
4. CORBA concepts.....	9
4.1. Quick tour of a working client&server.....	9
4.1.1. Definition of the object - the IDL	9
4.1.2. Identifying the Object	9
4.1.3. Calling the method.....	9
4.1.4. Moving the call across the network	10
4.1.5. Returning the answer	10
4.1.6. Continue.....	10
5. First CORBA Programs	11
5.1. Examples introduction.....	11
5.2. Files at a glance	11
5.3. Echo client & server	12
5.3.1. Echo client	13
5.3.2. Echo Server.....	17
5.3.3. Compiling server & client	23
5.4. Calculator client & server.....	24
5.4.1. Calculator client.....	25
5.4.2. Calculator server.....	28
5.4.3. Compiling server & client	36

5.5. Account client & server.....	37
5.5.1. Account client.....	37
5.5.2. Account server	40
5.5.3. Compiling server & client	46
5.6. Byte-Sequence client & server	47
5.6.1. Byte-Sequence client	47
5.6.2. Byte-Sequence server	51
5.6.3. Compiling client & server	57
5.7. BadCall client & server.....	58
5.7.1. BadCall client	58
5.7.2. BadCall server	63
5.7.3. Compiling client & server	69
5.8. NameResolve client & server.....	70
5.8.1. Example-Toolkit Helpers.....	71
5.8.2. NameResolve client	74
5.8.3. NameResolve server	76
5.8.4. Compiling client & server	82
5.9. Factory client & server	83
5.9.1. Factory client	84
5.9.2. Factory server	87
5.9.3. Compiling client & server	95
5.10. Threaded calculator server	96
5.10.1. multi-threaded calculator server	97
5.10.2. Compiling client & server	105
6. How to do garbage collection under CORBA	106
6.1. The question	106
6.2. Difference between the client and the server	106
6.3. Server-side deactivation	107
6.4. Why is this an issue?	108

List of Examples

5-1. Echo IDL file	12
5-2. echo-client.c.....	13
5-3. echo-server.c source code	17
5-4. echo-skelimpl.c.....	21
5-5. Makefile	23
5-6. Invoking make	24
5-7. Terminal 1 - Starting Echo Server	24
5-8. Terminal 2 - Starting Echo Client.....	24
5-9. calculator.idl	25
5-10. calculator-client.c	25
5-11. calculator-skelimpl.c.....	29
5-12. calculator-skelimpl.c fragment	31
5-13. calculator-server.c.....	32
5-14. makefile	36
5-15. account.idl.....	37
5-16. account-client.c.....	37
5-17. account-skelimpl.c fragment - object declaration.....	41
5-18. account-skelimpl.c fragment - method definition.....	41
5-19. account-skelimpl.c fragment - constructor	42
5-20. account-server.c	42
5-21. Makefile for the Account example	46
5-22. byteseq.idl.....	47
5-23. byteseq-client.c	47
5-24. byteseq-server.c	51
5-25. byteseq-skelimpl.c	54
5-26. Makefile	57
5-27. badcall.idl	58
5-28. badcall-client.c.....	59
5-29. badcall-server.c	63
5-30. badcall-skelimpl.c	66
5-31. Makefile	69
5-32. name-resolve.idl	70
5-33. example-toolkit.c(etk_get_name_service).....	71
5-34. example-toolkit.c(etk_name_service_bind)	71
5-35. example-toolkit.c(etk_name_service_resolve)	73
5-36. name-resolve-client.c.....	74
5-37. name-resolve-server.c	77
5-38. name-resolve-skelimpl.c	80
5-39. Makefile	82
5-40. factory.idl	83
5-41. factory-client.c.....	84
5-42. factory-server.c	87
5-43. factory-skelimpl.c	91
5-44. Makefile	96
5-45.	96
5-46. mt-calculator-server.c	97
5-47. calculator-skelimpl.c.....	102
5-48. Makefile	105

Chapter 1. Introduction

ORBit is an efficient, free C-based ORB, compliant to CORBA version 2.2. CORBA stands for Common Object Request Broker Architecture. CORBA in many ways is a successor to the Remote Procedure Call (RPC) system common on UNIX and other systems: the best oneline description of CORBA is that it is "Object Orientated RPC".

The key point about CORBA is that it provides a way for two programs to communicate information. The CORBA mechanism allows these two programs to be running on *different machines* and written in *different programming* languages while safely (and portably) exchanging data. They also could be running in the same program, on the same machine, in which case the process of communication is much quicker as ORBit recognises that it does not need to open any communication channel.

ORBit has some important features which distinguish it from other CORBA implementations. Firstly it is primarily a C-based implementation (using the standard C mapping), which many other CORBA implementations do not cater to. Secondly it is a fast implementation, meaning that it moves information on and off the communication channel into the programs quickly. Thirdly it is efficient in terms of its memory usage, meaning it can be run on small machines. Fourthly it works, and works in real life problems. Finally it is free software, that is free in terms of an open license to change the source code. This means that a number of different people (both academics and commercial people) can contribute to the source code and that bugs and problems can be fixed quickly. ORBit unsurprisingly is therefore licensed under the GNU Public License (GPL). More information about how the terms of this license affect you can be found in the FAQ, and you're encouraged to read the actual GPL text that comes in the distribution

The CORBA mechanism is ideal for classic client/server applications, say a graphical client GUI communicating to a database server, or much simpler applications, such as one program asking for a mail service from the CORBA system. ORBit was made principally for the latter case: that is communicating information between different programs running in a desktop environment (the Gnome environment). ORBit is a fully blown generic ORB and can be used in many other applications outside of the gnome desktop - there is absolutely no requirement to be running Gnome for ORBit.

This documentation is aimed principally at getting people with C programming experience started with ORBit and some discussion about the challenges of writing ORB aware software. If you are looking for a more fluffy description about what CORBA is I would start at the Resource section below. If you want to know the technical nitty-gritty about ORBit, go to the source code, or hang out on the ORBit mailing list.

It is also hoped that this documentation will be a starting point for a more technical orientated documentation about how ORBit is structured and the internal functions.

1.1. About this documentation

This documentation is currently maintained by Frank Rehberger frehberg@gnome.org (<mailto:frehberg@gnome.org>). For the definitive guide about what is going on, always go to the source code (with any luck, it will have documentation) or the C mapping document at the OMG. If you think there is

mistake with this documentation, please email me. If you would like to contribute an example or another chapter, please also get in contact, or post to the orbit mailing list.

This documentation was written with major contributions from Ewan Birney, Michael Launsch and Todd Lewis, edited by Stéphane Genaud, ORBit update by Frank Rehberger. It is written in docbook XML. You can get :

- The documentation and examples at <http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz>
(<http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz>)
- A PostScript version of this document at <http://www.gnome.org/projects/ORBit2/orbit-docs/orbit.ps>
(<http://www.gnome.org/projects/ORBit2/orbit-docs/orbit.ps>)
- A PDF version of this document at <http://www.gnome.org/projects/ORBit2/orbit-docs/orbit.pdf>
(<http://www.gnome.org/projects/ORBit2/orbit-docs/orbit.pdf>)

1.1.1. Change Notes between 1.5 and 1.4

- New sample "threaded-calculator" uses POA-setup THREAD_PER_REQUEST now, demonstrating usage of policies for child POAs. Furtheron Makefile has changed: Linker merges debug symbols of shared libraries correctly now into executable.

1.1.2. Change Notes between 1.4 and 1.3

- Adding new sample "threaded-calculator" demonstrating usage of ORBit2 as background task.
- For all samples initialize ORB with string "orbit-local-mt-orb", this string is valid for current ORB and also for older releases.

1.1.3. Change Notes between 1.3 and 1.2

- Port back to docbook4.1.2 used by gnome-doc project
- rename impl_*__destroy to impl_*__fini, being CORBA's nomenclature
- fix memory-leaks in server implementations: deactivate servants at termination

1.1.4. Change Notes between 1.2 and 1.1

- Introduced section for change notes

- fixing __destroy __fini confusion
- Add chapter for sample codes byteseq, badcall and name-resolve

Chapter 2. Frequently Asked Questions

This is to answer your questions about ORBit and Corba

2.1. General Questions

2.1.1. What is CORBA?

CORBA stands for Common Object Request Broker Architecture, standardized by the Object Management Group (OMG). It consists of an Interface Definition Language (IDL), language bindings and protocols to allow interoperation between applications

- written in different programming languages
- running in different processes
- developed for different operating systems

A more detailed answer to this question is available at <http://www.omg.org/gettingstarted>
(<http://www.omg.org/gettingstarted/>)

2.1.2. What is ORBit?

ORBit is an implementation of CORBA, which is used (amongst other things) in the GNOME project. Active development is done for ORBit2, being a clean re-implementation from scratch. The old ORBit code is no longer maintained.

2.1.3. Why aren't you using ILU/MICO/TAO?

Most of GNOME is written in C, both for performance reasons, and because C++ still isn't as portable and widely available. So integration with CORBA should use the IDL C mapping, which rules out TAO and MICO. ILU was ruled out because the license appeared as too restrictive at the time for free software.

2.1.4. Is ORBit stable?

ORBit is used in pretty much any GNOME application, which gives quite some testing for the features used. Other features have seen little or no testing.

2.1.5. Does ORBit work with other ORBs?

Yes. This is one of the primary features of CORBA, and available through the Internet Inter-ORB Protocol (IIOP). There is one pitfall: ORBit has a proprietary security mechanism to authenticate clients. If

interoperability is desired then you might have to figure out a work-around for this.

2.1.6. What license does ORBit get distributed with and how does it affect me?

The idl compiler is *GNU Public licensed* (GPL). The libraries are *Library GPL* (L-GPL) licensed. The code generated from the idl compiler have no restriction. Basically this means you can use ORBit in your own applications (including proprietary applications), the only restriction being that people whom you distribute your working code to must be able to update the ORBit libraries at will. If you wish to modify and distribute the ORBit idl compiler you have to distribute that modification under the GPL.

2.1.7. Why doesn't ORBit compile with my cc compiler ?

ORBit uses some of the extensions that gcc allows, including assignment to casts and void * pointer arithmetic. More current versions of ORBit will remove these and eventually it is likely the ORBit will compile with all ANSI C compilers.

You can always install gcc and use that. This will always work.

2.1.8. What is a language binding?

A language binding defines how to use the IDL operations in a programming language. There is a client-side mapping which explains how to call operations, and a server-side mapping which defines how to implement them. The client side mapping is largely implementation-independent.

On the server side, different 'object adapters' are provided by ORB vendors; only the 'Portable Object Adapter' (POA) implemented by ORBit allows portability between CORBA implementations.

2.1.9. What language bindings does ORBit provide?

At the moment only the C binding. Python and Perl bindings are being seriously talked about. Bindings (in various degrees of completeness) are also available for C++, Lisp, Pascal, Python, Ruby, and TCL; others are in-progress.

2.1.10. Does ORBit have DII and DSI?

Yes. Though beware that using DII and DSI in some cases requires the use of dynAny, which is not supported yet.

2.1.11. Does ORBit provide a naming service?

Yes. In addition, it is possible to use a third-party naming service, e.g. using the --ORBNameingIOR command line option. The 'Interoperable Naming' specification is not yet supported.

2.1.12. Can you encrypt a CORBA connection?

Yes, ORBit supports IIOP over SSL. the implementation is based on OpenSSL and support client and server side authentication. Frank O'Dwyer did initial work on this for ORBit.

2.2. Common Coding Problems

2.2.1. LD_LIBRARY_PATH not defined

ORBit uses dynamically loadable libraries and these need to be on the LD_LIBRARY_PATH for things to work.

2.2.2. IOR strings with newlines

When you get an object using a stringified IOR, make sure you trim the trailing newline from the string before passing it on.

2.2.3. Activating POAManager before servants can handle requests

You must activate the POAManager before incoming requests can be processed

```
PortableServer_POAManager_activate(PortableServer_POA__get_the_POAManager(poa,&ev),&ev)
```

Chapter 3. Installing ORBit

3.1. Installing from RPMS

The RPMS can be found on many web sites. The whole ORBit package is broken in two parts (as for most RPMS) : the `ORBit2` package contains the libraries to use it, and the `ORBit2-devel` package contains the necessary files to develop with ORBit, i.e. the idl compiler and the headers files.

I recommend the RPM repositories like <http://www.rpmfind.org> to find the RPMS that best suit your distribution. Though ORBit is probably installed if you already have GNOME installed, you must download the `ORBit-devel` to develop with ORBit.

Installation is quite simple : once the packages are downloaded, go:

```
bash $ rpm -Uvh ORBit2* ORBit2-devel*
```

Note that this will upgrade any previous rpm-based installation of ORBit.

3.2. Installing from Source

Installing from ORBit2 source code is very easy. You need to have glib version 2.0.0 or later series installed. To see if you have glib installed (and what version) go `glib-config --version`

You can obtain the latest version of glib from <http://www.gtk.org/>

Now just download the latest stable tar ball of ORBit. Start by going to the gnome web site (<http://www.gnome.org/>), choose download and find your closest mirror site.

ORBit installs as a standard gnu application, so going `./configure` followed by `make` and then getting root permissions and `make install` will do everything as expected.

What to do if you don't have root permissions Basically you want to run all of the above but with `./configure --prefix=<installation location>` which will install under `prefix/bin /libs` etc.

If ORBit2 2.7 does not compile with some commercial C compilers, this is because it uses a number of gcc extensions which are not supported elsewhere. *you can always download gcc and install that* for it to work.

3.3. Getting the examples to run

Once you have successfully installed orbit, getting the examples to run should be fine. The examples are

available by http from <http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz>
<http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz>) Gunzip and untar the package, perhaps like:

```
bash $gunzip -c orbit-docs.tar.gz | tar -xvf -
```

This should build a documentation directory that contains this documentation in both sgml (docbook) and html, and an examples directory. Move to the examples directory, and go

```
bash $./configure
bash $cd echo
bash $make
```

Proceed similarly for the calculator example.

To actually run the echo example, open two windows up. Run echo-server in one and echo-client in the other (echo-server writes out the file echo.ref which echo-client reads). If you want to have fun now, compile orbit on a different machine, make echo-client on the different machine, move echo.ref from the first machine to the second and run echo-client: eh voila - client/server over tcp/ip with the same code that ran using unix sockets on a single machine.

Note: From ORBit 0.5.3, IIOP communications over IP sockets are disabled by default for security reasons. You should create an `/etc/orbitrc` (for a system-wide settings), or an `~/.orbitrc` (for one user's setting) containing something like :

```
ORBIIOPUSock=1
ORBIIOPIPv4=1
ORBIIOPIPv6=0
```

Alternatively, you can also use command line parameters.

3.4. Known platforms where ORBit works

ORBit in theory is portable to any UNIX system (using the GNU configure system to define the system). Try it out - it will probably work. However, you may want to see if your platform has definitely been used before

- GNU/Linux, i386 Redhat/SuSE/Debian distributions
- GNU/Linux, alpha
- GNU/Linux, sparc
- Solaris 2.6 (UltraSparc)
- Digital UNIX 4.0
- FreeBSD 2.2.7-RELEASE (Intel)
- IRIX 6.2 (you can get it from <http://freeware.sgi.com>)

If you manage to compile it on any other platforms, let me know.

Chapter 4. CORBA concepts

Please skip this chapter and head straight to the first examples if you are the sort of person who understands better just by example. The examples chapter can be read without reading this chapter.

This chapter is to help you get an understanding of all the different terms that are bandied about ORBs and CORBA.

CORBA is a collection of standards defined by the Object Management Group (OMG - the sole purpose of the OMG is to provide a framework for people to agree on standards for CORBA). The OMG does not provide any working implementations of the CORBA standards, and so can be impartial. Most people who use CORBA only really keep one or two of these standards in their heads, but all the standards are free to be read from the OMG web site <http://www.omg.org/> (<http://www.omg.org/>). However it is good to have an idea about how all these standards fit together to provide CORBA.

4.1. Quick tour of a working client&server

The basic mechanism of CORBA is to run a method (that is a function) of an object from a separate program (in fact the program need not be separate, but don't worry about that yet). Going from one end of this to the other, this is what needs to be defined.

4.1.1. Definition of the object - the IDL

A definition of what methods can be called on what objects need to be provided for both the caller and callee. This is done using the *Interface Definition Language* or IDL of the object. The only information which is required to make a caller able to call an object on a remote server is the IDL of the object. Everything else is handled by the standards defined by the OMG.

4.1.2. Identifying the Object

The calling program needs to identify the (possibly remote) object somehow. This is done by something called an *IOR*, which can be represented as a string, and therefore used as an argument in the program. Decoding the IOR the client can tell the CORBA protocol and character encoding the server supports, beside much more details.

4.1.3. Calling the method

The calling program needs to actually call the method on the object somehow. This is done in the programming language of the caller, and the way the IDL of the maps to the programming language is standardised by the OMG. This is called the *Language Mapping*, and all the different ORBs provide at least one mapping. ORBit provides at the moment a C mapping.

Of course, C is a compiled language, so to write a C program which is going to make an ORBit call, one needs to compile the IDL of the object one wants to access using the orbit-idl compiler, and then write a C program which call functions that the orbit-idl compiler defines, compile this user written code along with the code generated for the client by the orbit compiler, and link it to the orbit and network libraries.

However for more dynamic languages (eg, Python), a more natural way of using CORBA is to dynamically load in the IDL definition and use it without any separate compile phase. The beauty of CORBA is that it supports both mechanisms

4.1.4. Moving the call across the network

The function call on the client now gets handled by the *Object Request Broker* or *ORB* and gets translated to the actual TCP/IP request to the server *ORB* which is handling the object to be called. The two ORBs communicate via a protocol called the *Internet InterOrb Protocol* or *IIOP*, which is standard. This means that the ORBs could come from different suppliers, and never had been tested against each other, and yet still work.

4.1.5. Returning the answer

On the server side, a mirror of the client process happens, translating the request from TCP/IP packets to an actual call in the programming language used to write the server. The servant object, written by whoever wrote the server then provides the return values, and the results are sent back down the ORBs to the client in reply message.

4.1.6. Continue

This may seem like a lot of work for a rather simple thing, but the idea about having so many standards is that some of the standards can change and adapt without everything in CORBA shifting. Learning about CORBA is usually much easier by example, so I would dip into the next chapter and come back to this one later.

Chapter 5. First CORBA Programs

5.1. Examples introduction

Three different, working programs will be presented in this chapter. They are all very simple and worth looking over and running (you will find the source code for them in the examples directory that comes with orbit-docs.tar.gz)

I have tested out the first two examples, echo and calculator and they work from the code in this document. The actual code with makefiles can be found at <http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz> (<http://www.gnome.org/projects/ORBit2/orbit-docs.tar.gz>). However, it is likely that the code is not well written as we would like, and I am sure it could get better. Please drop me a note if you would like to contribute something to the examples, preferably as patches to the code in examples directory and the orbit.xml document.

5.2. Files at a glance

Before we present these examples, we should sketch what files are generated or written by the programmer in a typical ORBit application. The load of files generated from the IDL specification may seem very complex at a first glance, and the following table tries to make clearer which files are really important. The first file the programmer must write in an ORBit application, is the IDL file. For a `f.idl` IDL specification, running

```
bash $orbit-idl-2 --skeleton-impl f.idl
```

will produce most of the needed files to start writing the application (you can see it as a framework). They are listed in the following table:

File	Usage
f-stubs.c	do not edit (translation of your IDL)
f-skels.c	do not edit (translation of your IDL)
f-common.c	do not edit (generated from IDL)
f.h	do not edit
f-skelimpl.c	add the code of the server methods

Files remaining to write :

f-client.c	write the client code
f-server.c	write the generic code for servant creation

The first three files deal with communication implementation and are automatically generated from your IDL file. The `f-skelimpl.c` file contains the framework of the servant functions: you should find near the end of the file, function prototypes corresponding to the one you have declared in your IDL, your real code must be inserted between markers. Of course, you should keep this file only on the server side since it is of no use for the client.

The `f-client.c` (you can choose another name) is to be written by the programmer. This is where the programmer initializes the ORB and binds the client to the server using the IOR.

The `f-server.c` (you can choose another name) must also be written but this part is rather generic and is usually copied from an existing application and hardly ever modified during the application developpement. It always deals with the ORB initialization and the POA creation so that servants are spawned to execute the server code defined in `f-skelimpl.c`.

5.3. Echo client & server

The aim for this example is to run a client which accepts typed input and this is printed out on the server on stdout

The echo functionality is represented in the following very short IDL.

Example 5-1. Echo IDL file

```
// MyFirstOrbit program - The Echo object
//
// All this does is pass a string from the
// client to the server.

interface Echo {
void echoString(in string input);
};
```

The *interface* definition is the key part of the definition. Each interface defines an object which can have methods on it. In this case there is one method, which takes a string argument and returns nothing. The *in* declaration before the argument indicates that this arguments is only passed into the method. Generally all arguments are in arguments, for the first case.

This idl is found in the file `echo.idl`. To compile the idl one does the following step: `$ orbit-idl-2 --skeleton-impl echo.idl` which will produce most of the needed files to start writing the *echo* application (you can see it as a framework). They are listed in the following table:

File	Usage for Client	Usage for Server
echo.h	readonly	readonly
echo-common.c	readonly	readonly
echo-stubs.c	readonly	-
echo-skels.c	-	readonly
echo-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with `echo-client.c` in following chapter.

echo-client.c	write the client code
echo-server.c	write the generic code for servant creation

5.3.1. Echo client

The client code is shown here

Example 5-2. echo-client.c

```
/*
 * Echo client program.. Hacked by Ewan Birney <birney@sanger.ac.uk>
 * from echo test suite, update for ORBit2 by Frank Rehberger
 * <F.Rehberger@xtradyne.de>
 *
 * Client reads object reference (IOR) from local file 'echo.ref' and
 * forwards console input to echo-server. A dot . as single character
 * in input terminates the client.
 */

#include <stdio.h>
#include <signal.h>
#include <orbit/orbit.h>

/*
 * This header file was generated from the idl
 */

#include "echo.h"

/**
 * test for exception
 */
static
gboolean
raised_exception(CORBA_Environment *ev)
{
return ((ev)->_major != CORBA_NO_EXCEPTION);
}

/**
 * in case of any exception this macro will abort the process
 */
static
void
abort_if_exception(CORBA_Environment *ev, const char* mesg)
{
if (raised_exception (ev)) {
g_error ("%s %s", mesg, CORBA_exception_id (ev));
CORBA_exception_free (ev);
abort();
}
}
```

```

}

static CORBA_ORB  global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment  local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int           *argc_ptr,
             char          *argv[],
             CORBA_ORB      *orb,
             CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (raised_exception(ev)) return;
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB           orb,
                CORBA_Object       service,
                CORBA_Environment *ev)
{
    /* releasing managed object */
}

```

```

CORBA_Object_release(service, ev);
if (raised_exception(ev)) return;

/* tear down the ORB */
if (orb != CORBA_OBJECT_NIL)
{
    /* going to destroy orb.. */
    CORBA_ORB_destroy(orb, ev);
    if (raised_exception(ev)) return;
}
}

/***
 *
 */
static
CORBA_Object
client_import_service_from_stream (CORBA_ORB           orb,
                                  FILE              *stream,
                                  CORBA_Environment *ev)
{
CORBA_Object obj = CORBA_OBJECT_NIL;
gchar *objref=NULL;

fscanf (stream, "%as", &objref); /* FIXME, handle input error */

obj = (CORBA_Object) CORBA_ORB_string_to_object (global_orb,
    objref,
    ev);
free (objref);

return obj;
}

/***
 *
 */
static
CORBA_Object
client_import_service_from_file (CORBA_ORB           orb,
                                 char             *filename,
                                 CORBA_Environment *ev)
{
    CORBA_Object   obj      = NULL;
    FILE          *file     = NULL;

    /* write objref to file */

    if ((file=fopen(filename, "r"))==NULL)
        g_error ("could not open %s\n", filename);

obj=client_import_service_from_stream (orb, file, ev);

fclose (file);

return obj;
}

```

```

/***
 *
 */
static
void
client_run (Echo echo_service,
            CORBA_Environment *ev)
{
char filebuffer[1024+1];

g_print("Type messages to the server\n"
"a single dot in line will terminate input\n");

while( fgets(filebuffer,1024,stdin) ) {
if( filebuffer[0] == '.' && filebuffer[1] == '\n' )
break;

/* chop the newline off */
filebuffer[strlen(filebuffer)-1] = '\0';

/* using the echoString method in the Echo object
 * this is defined in the echo.h header, compiled from
 * echo.idl */

Echo_echoString(echo_service,filebuffer,ev);
if (raised_exception (ev)) return;
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
CORBA_char filename[] = "echo.ref";

Echo echo_service = CORBA_OBJECT_NIL;

CORBA_Environment ev[1];
CORBA_exception_init(ev);

client_init (&argc, argv, &global_orb, ev);
abort_if_exception(ev, "init failed");

g_print ("Reading service reference from file \"%s\"\n", filename);

echo_service = (Echo) client_import_service_from_file (global_orb,
            "echo.ref",
            ev);
abort_if_exception(ev, "import service failed");

client_run (echo_service, ev);
abort_if_exception(ev, "service not reachable");
}

```

```

client_cleanup (global_orb, echo_service, ev);
    abort_if_exception(ev, "cleanup failed");

    exit (0);
}

```

The client can be broken down into three distinct sections.

- Initialising the ORB
- Getting the Object
- Using the Object

The key part of the client is when it calls the echoString method on the server. The idl definition

```
void echoString(in string input);
```

Ends up becoming the following definition in the echo.h header file generated from the idl

```
extern void Echo_echoString(Echo           obj,
                           CORBA_char      *astring,
                           CORBA_Environment *ev);
```

This follows the accepted rules for Object based programming in C, that is

- The Object is passed in as the first argument to the function
- The method name is qualified by the object name beforehand
- Exceptions are handled by a structure that is passed in as the last argument to the function

Of course, you don't have to follow this in your own code, but this is how the CORBA C mapping works, and it is not a bad solution.

5.3.2. Echo Server

The server is basically more complicated than the client, but has some commonality with the client. The server has to at the end of the day go into a main loop where it listens to connections. Before that it has to create the ORB and bind its own implementations of the objects to the ORB.

In real life servers, this gets much more complicated, but as this is an example, it is pretty simple once you get through the ORB initialisation process.

Example 5-3. echo-server.c source code

```

/*
 * echo-server program. Hacked from Echo test suite by
 * <birney@sanger.ac.uk>, ORBit2 update by Frank Rehberger
 * <F.Rehberger@xtradyne.de>
 */

#include <stdio.h>
#include <stdlib.h>

```

```

#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "echo-skelimpl.c"
#include "examples-toolkit.h" /* provides etk_abort_if_exception */

static CORBA_ORB          global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA root_poa   = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
server_init (int             *argc_ptr,
            char           *argv[],
            CORBA_ORB      *orb,
            PortableServer_POA *poa,
            CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
    goto failed_orb;

    (*poa) = (PortableServer_POA)

```

```

CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
goto failed_poa;

    poa_manager = PortableServer_POA__get_the_POAManager(*poa, ev);
if (etk_raised_exception(ev))
goto failed_poamanager;

PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB             orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(.) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB             orb,
                PortableServer_POA  poa,
                CORBA_Object        ref,
                CORBA_Environment   *ev)
{
PortableServer_ObjectId  *objid      = NULL;

    objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivation - will invoke __fini destructor */
PortableServer_POA_deactivate_object (poa, objid, ev);
}

```

```

if (etk_raised_exception(ev)) return;

PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (objid);

CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

/* ORB: tear down the ORB */
if (orb != CORBA_OBJECT_NIL)
{
    /* going to destroy orb.. */
    CORBA_ORB_destroy(orb, ev);
}
if (etk_raised_exception(ev)) return;
}

/*
 * Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB                orb,
                        PortableServer_POA   poa,
                        CORBA_Environment   *ev)
{
Echo  ref = CORBA_OBJECT_NIL;

ref = impl_Echo__create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * main
*/
int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "echo.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

```

```

servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

etk_export_object_to_file (global_orb,
    servant,
    filename,
    ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

exit (0);
}

```

The key part of the server is when it calls **servant = impl_Echo_create (poa, ev);**. This is a function defined in file echo-skelimpl.c being included at top of echo-server.c. For each object method of echo object interface file echo-skelimpl.c contains a predefined implementation that must be extended by user (specific regions are marked by comments); incoming requests are delegated by object manager to specific method implementation. - For echo server application only a single line for method **echoString(..)** must be inserted, this line will print the echo-string to console. Let's have a look at echo-skelimpl.c that has been generated by **orbit-idl-2** tool as template for user. Therefor only a single line has been added by user **g_print ("%s\n", input);** at very end of file in function body *impl_Echo_echoString(..)*.

Note: Constructor (**__create**) and Destructor (**__fini**) are defined, too. How to extend those functions defining lifecycle of objects will be subject to next chapters.

Example 5-4. echo-skelimpl.c

```

#include "echo.h"

/** App-specific servant structures **/

typedef struct
{
    POA_Echo servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    /* ----- ----- end ----- */
}
impl_POA_Echo;

/** Implementation stub prototypes ***/

```

```

static void impl_Echo__fini(impl_POA_Echo * servant,
    CORBA_Environment * ev);
static void
impl_Echo_echoString(impl_POA_Echo * servant,
    const CORBA_char * input, CORBA_Environment * ev);

/*** epv structures ***/

static PortableServer_ServantBase__epv impl_Echo_base_epv = {
    NULL, /* _private data */
    (gpointer) &impl_Echo__fini, /* finalize routine */
    NULL, /* default_POA routine */
};

static POA_Echo__epv impl_Echo_epv = {
    NULL, /* _private */
    (gpointer) &impl_Echo_echoString,
};

/*** vepv structures ***/

static POA_Echo__vepv impl_Echo_vepv = {
    &impl_Echo_base_epv,
    &impl_Echo_epv,
};

/*** Stub implementations ***/

static Echo
impl_Echo__create(PortableServer_POA poa, CORBA_Environment * ev)
{
    Echo retval;
    impl_POA_Echo *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Echo, 1);
    newservant->servant.vepv = &impl_Echo_vepv;
    newservant->poa =
        (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);
    POA_Echo__init((PortableServer_Servant) newservant, ev);
    /* Before servant is going to be activated all
     * private attributes must be initialized. */

    /* ----- init private attributes here ----- */
    /* ----- ----- end ----- */

    objid = PortableServer_POA_activate_object(poa, newservant, ev);
    CORBA_free(objid);
    retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

    return retval;
}

static void
impl_Echo__fini(impl_POA_Echo * servant, CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);
}

```

```

/* No further remote method calls are delegated to
 * servant and you may free your private attributes. */
/* ----- free private attributes here ----- */
/* ----- ----- end ----- */

POA_Echo__fini((PortableServer_Servant) servant, ev);

g_free(servant);
}

static void
impl_Echo_echoString(impl_POA_Echo * servant,
                     const CORBA_char * input, CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
    g_print ("%s\n", input);
    /* ----- ----- end ----- */
}

```

5.3.3. Compiling server & client

The following makefile can be used to compile both, the client and the server. Be aware of the location of ORBit : on my system it has been installed under /usr but it could be /usr/local if you have built it from the sources, and hence the path for ORBIT variables below may vary. If using ORBit binary packages shipped with your Linux or BSD/Unix distribution the makefile below will do.

Example 5-5. Makefile

```

PREFIX ?= /usr
CC = gcc
TARGETS=echo-client echo-server
ORBIT_IDL=orbit-idl-2
CFLAGS=-g -DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
      -I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
      -I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \
      -ldl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm
IDLOUT=echo-common.c echo-stubs.c echo-skels.c echo.h

all: $(IDLOUT) echo-client echo-server

echo-server.o : echo-server.c echo-skelimpl.c

echo-client : echo-client.o echo-common.o echo-stubs.o
echo-server : echo-server.o echo-common.o echo-skels.o

$(IDLOUT): echo.idl
      $(ORBIT_IDL) echo.idl

clean:
      rm -rf *.o *~ $(IDLOUT)

distclean: clean

```

```
rm -rf echo-client echo-server
```

Example 5-6. Invoking make

```
[frehberg@papaya echo]$ make
orbit-idl-2 echo.idl
orbit-idl-2 2.4.1 compiling
  small mode, show preprocessor errors, passes: stubs skels common headers
  skel_impl imodule

gcc -DORBIT2=1 -D_REENTRANT -I/usr/include/orbit-2.0 -I/usr/include/linc-1.0
-I/usr/include/glib-2.0 -I/usr/lib/glib-2.0/include -c -o echo-client.o
echo-client.c
gcc -DORBIT2=1 -D_REENTRANT -I/usr/include/orbit-2.0 -I/usr/include/linc-1.0
-I/usr/include/glib-2.0 -I/usr/lib/glib-2.0/include -c -o echo-common.o
echo-common.c
gcc -DORBIT2=1 -D_REENTRANT -I/usr/include/orbit-2.0 -I/usr/include/linc-1.0
-I/usr/include/glib-2.0 -I/usr/lib/glib-2.0/include -c -o echo-stubs.o
echo-stubs.c
gcc -Wl,--export-dynamic -lORBit-2 -llinc -lgmodule-2.0 -ldl -lgobject-2.0
-lgthread-2.0 -lpthread -lglib-2.0 -lm echo-client.o echo-common.o
echo-stubs.o -o echo-client
gcc -DORBIT2=1 -D_REENTRANT -I/usr/include/orbit-2.0 -I/usr/include/linc-1.0
-I/usr/include/glib-2.0 -I/usr/lib/glib-2.0/include -c -o echo-server.o
echo-server.c
gcc -DORBIT2=1 -D_REENTRANT -I/usr/include/orbit-2.0 -I/usr/include/linc-1.0
-I/usr/include/glib-2.0 -I/usr/lib/glib-2.0/include -c -o echo-skels.o
echo-skels.c
gcc -Wl,--export-dynamic -lORBit-2 -llinc -lgmodule-2.0 -ldl -lgobject-2.0
-lgthread-2.0 -lpthread -lglib-2.0 -lm echo-server.o echo-common.o
echo-skels.o -o echo-server
```

After calling **make** in terminal window all sources have been compiled and you should open a second terminal window. In the first window we will start the server with the command: **./echo-server**. The server should print a very long string into the file **echo.ref**, starting with the 4 character sequence **IOR**: In the second window we will print content of **echo.ref** to console and start the client with the command **./echo-client**. You should not try to type the IOR string, instead use the cut and paste functionality of your terminal.

Example 5-7. Terminal 1 - Starting Echo Server

```
[frehberg@papaya echo]$ ./echo-server
```

Example 5-8. Terminal 2 - Starting Echo Client

```
[frehberg@papaya echo]$ cat echo.ref
IOR:01000000d00000049444c3a4563686f3a312e300000000003000000054424f540000000101
020005000000554e4958000000000700000070617061796100002e0000002f746d702f6f72626974
2d66726568626572672f6c696e632d323230662d302d3235323566633235373064303400000000000
0000caaedfba5800000010102002e0000002f746d702f6f726269742d66726568626572672f6c69
6e632d323230662d302d323532356663323537306430340000001c000000000000a6361450d7ea
e8a8dc29282828282801000008af91bdf0100000048000000100000002000000050000001c00
0000000000a6361450d7ae8a8dc292828282801000008af91bdf01000000140000000100
00000100010500000000901010000000000
[frehberg@papaya echo]$ ./echo-client
Type messages to the server
a single dot in line will terminate input:
```

5.4. Calculator client & server

This example will take you further into understanding how to actually make a working server, using the support that comes from ORBit. It will demonstrate handling of replies from server.

The system will not be doing very much. The server just provides two functions, one to add two numbers and one to subtract two numbers. The first thing you have to do is to write the IDL files for the server. In our example it is very simple.

Example 5-9. calculator.idl

```
interface Calculator
{
    double add(in double number1, in double number2);
    double sub(in double number1, in double number2);
};
```

Then you have to generate the skeleton and stub files. In addition to these two files the ORBit IDL compiler also generates a common file and a header file. The common file implements the memory management functions and other things, useful in the client as well as in the server. The sequence to generate the C source files is rather simple. `$ orbit-idl-2 --skeleton-impl calculator.idl` generates all the files we will use in this example.

File	Usage for Client	Usage for Server
calculator.h	readonly	readonly
calculator-common.c	readonly	readonly
calculator-stubs.c	readonly	-
calculator-skels.c	-	readonly
calculator-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with *calculator-client.c* in following chapter.

calculator-client.c	write the client code
calculator-server.c	write the generic code for servant creation

5.4.1. Calculator client

The next thing you have to do is to write the server and client programs. We start with the client, because it's easier and not very complicated.

A simple implementation of the client might look like this

Example 5-10. calculator-client.c

```

/* calculator-client.c hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>. */

#include <assert.h>
#include <signal.h>
#include <stdio.h>
#include <orbit/orbit.h>

#include "calculator.h"

#include "examples-toolkit.h"

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int             *argc_ptr,
            char          *argv[],
            CORBA_ORB      *orb,
            CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

```

```

}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB                 orb,
                CORBA_Object            service,
                CORBA_Environment       *ev)
{
    /* releasing managed object */
    CORBA_Object_release(service, ev);
    if (etk_raised_exception(ev)) return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev)) return;
    }
}

/***
 *
 */
static
void
client_run (Calculator           service,
            CORBA_Environment *ev)
{
    CORBA_double      result=0.0;

    /*
     * use calculator service
     */

    result = Calculator_add(service, 1.0, 2.0, ev);
    if (etk_raised_exception (ev)) return;

    /* prints results to console */
    g_print("Result: 1.0 + 2.0 = %2.0f\n", result);
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
    CORBA_char  filename[] = "calculator.ref";

    Calculator service = CORBA_OBJECT_NIL;

    CORBA_Environment ev[1];
}

```

```

CORBA_exception_init(ev);

client_init (&argc, argv, &global_orb, ev);
etk_abort_if_exception(ev, "init failed");

g_print ("Reading service reference from file \"%s\"\n", filename);

service = (Calculator) etk_import_object_from_file (global_orb,
    filename,
    ev);
    etk_abort_if_exception(ev, "import service failed");

client_run (service, ev);
    etk_abort_if_exception(ev, "service not reachable");

client_cleanup (global_orb, service, ev);
    etk_abort_if_exception(ev, "cleanup failed");

exit (0);
}

```

Rather simple, but full of unexplained stuff. Let's take a close look to the defined variables.

env

This variable is used to hold information about exceptions which might have occurred during a function call. How to use this variable to detect errors in function will be explained in a later example.

orb

This is the ORB itself.

server

This is the object reference to the server.

The example above is a full functional client. The magic in this example is the usage of the function *CORBA_ORB_string_to_object* with the parameter *argv[1]*. The explanation is that the program is supposed to be called with the string representation of the Calculator server as the first parameter. How to obtain this string, will be shown in the next example, where I describe how the server.

5.4.2. Calculator server

To implement the server, the IDL compiler does a great deal of work for you. It can emit all the stuff necessary to set up the data structures and function calls for the server implementation. All you have to write is the setup stuff in your main function and the actual implementation of the server functions. First I'll present the functions and data structures the IDL compiler generates and then I'll show what's necessary to set up the environment for these functions to work properly.

5.4.2.1. Calculator Implementation Skeleton

To ease the task of implementing the calculator the ORBit IDL compiler can output an implementation skeleton of the server. This is enabled with the --skeleton-impl switch to the IDL compiler. The output of **orbit-idl-2 --skeleton-impl calculator.idl** looks like this (the default name for the generated source file is `calculator-skelimpl.c`):

Example 5-11. calculator-skelimpl.c

```
#include "calculator.h"

/** App-specific servant structures **/


typedef struct
{
    POA_Calculator servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    /* ----- ----- end ----- */
}
impl_POA_Calculator;

/** Implementation stub prototypes **/


static void impl_Calculator_fini(impl_POA_Calculator * servant,
    CORBA_Environment * ev);
static CORBA_double
impl_Calculator_add(impl_POA_Calculator * servant,
    const CORBA_double number1,
    const CORBA_double number2,
    CORBA_Environment * ev);

static CORBA_double
impl_Calculator_sub(impl_POA_Calculator * servant,
    const CORBA_double number1,
    const CORBA_double number2,
    CORBA_Environment * ev);

/** epv structures **/


static PortableServer_ServantBase__epv impl_Calculator_base_epv = {
    NULL, /* _private data */
    (gpointer) & impl_Calculator_fini, /* finalize routine */
    NULL, /* default_POA routine */
};

static POA_Calculator__epv impl_Calculator_epv = {
    NULL, /* _private */
    (gpointer) & impl_Calculator_add,
    (gpointer) & impl_Calculator_sub,
};

/** vepv structures **/



```

```

static POA_Calculator__vepv impl_Calculator_vepv = {
    &impl_Calculator_base_epv,
    &impl_Calculator_epv,
};

/** Stub implementations **/


static Calculator
impl_Calculator__create(PortableServer_POA poa,
                       CORBA_Environment * ev)
{
    Calculator retval;
    impl_POA_Calculator *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Calculator, 1);
    newservant->servant.vepv = &impl_Calculator_vepv;
    newservant->poa = poa;
    POA_Calculator__init((PortableServer_Servant) newservant, ev);
    /* Before servant is going to be activated all
     * private attributes must be initialized. */

    /* ----- init private attributes here ----- */
    /* ----- ----- end ----- */

    objid = PortableServer_POA_activate_object(poa, newservant, ev);
    CORBA_free(objid);
    retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

    return retval;
}

static void
impl_Calculator__fini (impl_POA_Calculator * servant,
                      CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);

    /* No further remote method calls are delegated to
     * servant and you may free your private attributes. */
    /* ----- free private attributes here ----- */
    /* ----- ----- end ----- */

    POA_Calculator__fini((PortableServer_Servant) servant, ev);

    g_free (servant);
}

static CORBA_double
impl_Calculator_add(impl_POA_Calculator * servant,
                    const CORBA_double number1,
                    const CORBA_double number2,
                    CORBA_Environment * ev)
{
    CORBA_double retval;

    /* ----- insert method code here ----- */

```

```

    retval = number1 + number2;
    /* ----- ----- end ----- */
    return retval;
}

static CORBA_double
impl_Calculator_sub(impl_POA_Calculator * servant,
                     const CORBA_double number1,
                     const CORBA_double number2,
                     CORBA_Environment * ev)
{
    CORBA_double retval;

    /* ----- insert method code here ----- */
    retval = number1 - number2;
    /* ----- end ----- */
    return retval;
}

```

This source file provides you with most of the magic of a server. Note that we generate this file (with the **--skeleton-impl** switch) only once, and then the makefile invokes **orbit-idl-2** with no switch. If you call **orbit-idl-2 --skeleton-impl** from the makefile, the previous file will be overwritten and your implementation code lost. Once the implementation code is written, just include the source file at the beginning of the **calculator-server.c** file.

For this first example, I won't explain all the bits and pieces of the generated source file. This will be done later. We'll just concentrate on getting the server running.

As you see there are two functions:

```
CORBA_double impl_Calculator_add(impl_POA_Calculator* servant, CORBA_double
number1, CORBA_double number2, CORBA_Environment* ev);
```

and

```
CORBA_double impl_Calculator_sub(impl_POA_Calculator* servant, CORBA_double
number1, CORBA_double number2, CORBA_Environment* ev);
```

These two functions are implementing the function defined in the IDL file. Because the IDL compiler doesn't provide you with a real implementation (it doesn't know what the function should do), you have to extend this skeleton yourself where marked.

The **impl_Calculator_add()** should add it's two parameters and return the result so this function should be changed into:

Example 5-12. calculator-skelimpl.c fragment

```

static CORBA_double
impl_Calculator_add(impl_POA_Calculator * servant,
                     const CORBA_double number1,
                     const CORBA_double number2,
                     CORBA_Environment * ev)
{
    CORBA_double retval;

    /* ----- insert method code here ----- */
    retval = number1 + number2;
    /* ----- ----- end ----- ----- */

    return retval;
}

```

5.4.2.2. Calculator Server Implementation

The things you need in your minimal main function to make things work can be implemented in the following way, note analogy to `echo-server.c` of previous example.

Example 5-13. calculator-server.c

```

/*
 * calculator-server program. Hacked from Frank Rehberger
 * <F.Rehberger@xtradyne.de>.
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <corbit/orbit.h>

#include "calculator.h"
#include "calculator-skelimpl.c"

#include "examples-toolkit.h"

static CORBA_ORB           global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA  root_poa  = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

```

```

        if (global_orb != CORBA_OBJECT_NIL)
        {
            CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
            etk_abort_if_exception (local_ev, "caught exception");
        }
    }

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
server_init (int             *argc_ptr,
             char          *argv[],
             CORBA_ORB     *orb,
             PortableServer_POA *poa,
             CORBA_Environment *ev)
{
    PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    /* init signal handling */
    signal(SIGINT, server_shutdown);
    signal(SIGTERM, server_shutdown);

    /* create Object Request Broker (ORB) */

        (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev))
        goto failed_orb;

        (*poa) = (PortableServer_POA)
    CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
    if (etk_raised_exception(ev))
        goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
    if (etk_raised_exception(ev))
        goto failed_poamanager;

    PortableServer_POAManager_activate(poa_manager, ev);
    if (etk_raised_exception(ev))
        goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
    return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
    CORBA_ORB_destroy(*orb, local_ev);
}

```

```

failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB           orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(..) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB           orb,
                PortableServer_POA poa,
                CORBA_Object       ref,
                CORBA_Environment *ev)
{
PortableServer_ObjectId   *objid      = NULL;

    objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

    /* Servant: deactivation - will invoke __fini destructor */
    PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

    PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

    CORBA_free (objid);

    CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

    CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

    /* ORB: tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
    }
}

```

```

}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB          orb,
                        PortableServer_POA poa,
                        CORBA_Environment *ev)
{
Calculator ref = CORBA_OBJECT_NIL;

    ref = impl_Calculator__create (poa, ev);
    if (etk_raised_exception(ev))
        return CORBA_OBJECT_NIL;

    return ref;
}

/*
 * main
 */
int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "calculator.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

    server_init (&argc, argv, &global_orb, &root_poa, ev);
    etk_abort_if_exception(ev, "failed ORB init");

    servant = server_activate_service (global_orb, root_poa, ev);
    etk_abort_if_exception(ev, "failed activating service");

    g_print ("Writing service reference to: %s\n\n", filename);

    etk_export_object_to_file (global_orb,
                               servant,
                               filename,
                               ev);
    etk_abort_if_exception(ev, "failed exporting IOR");

    server_run (global_orb, ev);
    etk_abort_if_exception(ev, "failed entering main loop");

    server_cleanup (global_orb, root_poa, servant, ev);
    etk_abort_if_exception(ev, "failed cleanup");

exit (0); }

```

I'm not going to explain every line of this example yet; you only need to know that it creates a servant object whose object-reference is written to file "calculator.ref". File-IO is done using specific function from "example-toolkit" laying beside each example; the file contains a string always starting with the magic sequence "IOR:" and is read by client application to get hold of servants object-reference. The IOR string contains sufficient information to get to know host, port and object key within server. ORBit2 provides tools to decode the IOR string, namely **ior-decode-2**.

5.4.3. Compiling server & client

The following makefile can be used to compile both, the client and the server. Be aware of the location of ORBit : on my system it has been installed under /usr but it could be /usr/local if you have built it from the sources, and hence the path for ORBIT variables below may vary. If using ORBit binary packages shipped with Linux or BSD/Unix the simple makefile below will do.

Example 5-14. makefile

```
PREFIX ?= /usr
CC = gcc
TARGETS=calculator-client calculator-server
ORBIT_IDL=orbit-idl-2
CFLAGS=-DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
      -I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
      -I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBIT-2 -llinc -lgmodule-2.0 \
      -ldl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm
IDLOUT=calculator-common.c calculator-stubs.c calculator-skels.c calculator.h

all: $(IDLOUT) calculator-client calculator-server

calculator-server.o : calculator-server.c calculator-skelimpl.c

calculator-client : calculator-client.o calculator-common.o calculator-stubs.o
calculator-server : calculator-server.o calculator-common.o calculator-skels.o

$(IDLOUT): calculator.idl
    $(ORBIT_IDL) calculator.idl

clean:
    rm -rf *.o *~ $(IDLOUT)

distclean: clean
    rm -rf calculator-client calculator-server
```

After calling **make** in terminal window all sources have been compiled and you should open a second terminal window. In the first window we will start the server with the command: **calculator-server > calculator.ref**. The server should print a very long string into the file **calculator.ref**, starting with the 4 character sequence **IOR:** In the second window we start the client with the command **calculator-client ‘cat calculator.ref’**

IOR-string. You should not try to type the IOR string, instead use the cut and paste functionality of your xterm or whatever you are using.

If everything works, you should get the following output: Result: 1.0 + 2.0 = 3.

5.5. Account client & server

In this third simple example, we will see how we can set up a client that can modify the value of a variable stored on the server. It is basically the way an account manager works. The stored variable here is balance. The idl definition (`account.idl`) for our account is :

Example 5-15. `account.idl`

```
interface Account {
    void deposit (in unsigned long amount);
    void withdraw (in unsigned long amount);
    readonly attribute long balance;
};
```

Then you have to generate the skeleton and stub files. In addition to these two files the ORBit IDL compiler also generates a common file and a header file. The common file implements the memory management functions and other things, useful in the client as well as in the server. The sequence to generate the C source files is rather simple. `$ orbit-idl-2 --skeleton-impl account.idl` generates all the files we will use in this example.

File	Usage for Client	Usage for Server
account.h	readonly	readonly
account-common.c	readonly	readonly
account-stubs.c	readonly	-
account-skels.c	-	readonly
account-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with `account-client.c` in following chapter.

account-client.c	write the client code
account-server.c	write the generic code for servant creation

5.5.1. Account client

There is no difficulty in setting the client (at least no more than in the previous examples). Only one thing has been added : we test for the availability of the server (`if (!acc_client) ...`) before invoking calls to the server.

Example 5-16. account-client.c

```

/* account-client.c hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>. */

#include <assert.h>
#include <signal.h>
#include <stdio.h>
#include <orbit/orbit.h>

#include "account.h"

#include "examples-toolkit.h" /* ie. etk_abort_if_exception() */

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int             *argc_ptr,
             char          *argv[],
             CORBA_ORB      *orb,
             CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

```

```

}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB                 orb,
                CORBA_Object            service,
                CORBA_Environment       *ev)
{
    /* releasing managed object */
    CORBA_Object_release(service, ev);
    if (etk_raised_exception(ev)) return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev)) return;
    }
}

/***
 *
 */
static
void
client_run (Account           service,
            CORBA_long      amount,
            CORBA_Environment *ev)
{
CORBA_long balance=0;

/*
 * use calculator server
 */

    balance = Account__get_balance (service, ev);
if (etk_raised_exception (ev)) return;

    g_print ("balance %5d, ", balance);

    if (amount > 0)
    {
        Account_deposit (service, amount, ev);
        if (etk_raised_exception (ev)) return;
    }
    else
    {
        Account_withdraw (service, abs(amount), ev);
        if (etk_raised_exception (ev)) return;
    }

    balance = Account__get_balance (service, ev);
if (etk_raised_exception (ev)) return;
}

```

```

        g_print ("new balance %5d\n", balance);
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
    CORBA_char      filename[] = "account.ref";
    CORBA_long      amount=0;

    Account service = CORBA_OBJECT_NIL;

    CORBA_Environment ev[1];
    CORBA_exception_init(ev);

    client_init (&argc, argv, &global_orb, ev);
    etk_abort_if_exception(ev, "init failed");

    if (argc<2) g_error ("usage: %s <amount>", argv[0]);

    amount = atoi(argv[1]);

    g_print ("Reading service reference from file \"%s\"\n", filename);

    service = (Account) etk_import_object_from_file (global_orb,
filename,
ev);
    etk_abort_if_exception(ev, "import service failed");

    client_run (service, amount, ev);
    etk_abort_if_exception(ev, "service not reachable");

    client_cleanup (global_orb, service, ev);
    etk_abort_if_exception(ev, "cleanup failed");

    exit (0);
}

```

5.5.2. Account server

5.5.2.1. Account server Skeleton Implementation

For the server, like in the previous example, we first generate the source file `account-skelimpl.c` that will receive the implementation code for the methods. This is done once again with `orbit-idl-2 --skeleton-impl account.idl`.

Now, let us edit `account-skelimpl.c`. We search for the the `balance` attribute that was declared in the IDL file. At the beginning of the file, we can spot the way it has been translated into C by the idl compiler:

Example 5-17. account-skelimpl.c fragment - object declaration

```
typedef struct
{
    POA_Account servant;
    PortableServer_POA poa;

    CORBA_long attr_balance;

    /* ----- add private attributes here ----- */
    CORBA_long attr_balance;
    /* ----- ----- end ----- */
}
impl_POA_Account;
```

So, the server methods (`withdraw` and `deposit`) will have to manage the balance of the account through the `servant->attr_balance` (the servant variable is passed as parameter to each method).

Now, let us get to the end of the file and find the methods stubs. We find the `impl_Account_*` functions, to which we add the implementation code. This could be:

Example 5-18. account-skelimpl.c fragment - method definition

```
static void
impl_Account_deposit(impl_POA_Account * servant,
                      const CORBA_unsigned_long amount, CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
    servant->attr_balance += amount;
    /* ----- ----- end ----- */
}

static void
impl_Account_withdraw(impl_POA_Account * servant,
                      const CORBA_unsigned_long amount,
                      CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
    servant->attr_balance -= amount;
    /* ----- ----- end ----- */
}

static CORBA_long
impl_Account__get_balance(impl_POA_Account * servant, CORBA_Environment * ev)
{
    CORBA_long retval;

    /* ----- insert method code here ----- */
    retval = servant->attr_balance;
    /* ----- ----- end ----- */

    return retval;
}
```

The missing key stone is the constructor that establishes initial, consistent state for object on creation.

Example 5-19. account-skelimpl.c fragment - constructor

```
...
static Account
impl_Account__create(PortableServer_POA poa, CORBA_Environment * ev)
{
    Account retval;
    impl_POA_Account *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Account, 1);
    newservant->servant.vepv = &impl_Account_vepv;
    newservant->poa =
        (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);
    POA_Account__init((PortableServer_Servant) newservant, ev);
    /* Before servant is going to be activated all
     * private attributes must be initialized. */

    /* ----- init private attributes here ----- */
    newservant->attr_balance = 0;
    /* ----- ----- end ----- ----- */

    objid = PortableServer_POA_activate_object(poa, newservant, ev);
    CORBA_free(objid);
    retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

    return retval;
}
..
```

5.5.2.2. Account server implementation

Lastly, we have to write a rather generic code to set up the server. We call it `account-server.c`. It is roughly the same code as in the calculator and echo examples. The code just initializes the ORB and publishes an IOR for the server object.

Example 5-20. account-server.c

```
/*
 * account-server program. Hacked from Frank Rehberger
 * <F.Rehberger@xtradyne.de>.
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "account.h"
#include "account-skelimpl.c"
```

```

#include "examples-toolkit.h" /* provides etk_abort_if_exception */

static CORBA_ORB           global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA   root_poa  = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
server_init (int             *argc_ptr,
            char            *argv[],
            CORBA_ORB       *orb,
            PortableServer_POA *poa,
            CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
    goto failed_orb;

    (*poa) = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
    goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
}

```

```

if (etk_raised_exception(ev))
goto failed_poamanager;

PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
goto failed_activation;

CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB             orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(.) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB             orb,
                PortableServer_POA  poa,
                CORBA_Object        ref,
                CORBA_Environment   *ev)
{
PortableServer_ObjectId  *objid      = NULL;

    objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

    /* Servant: deactivate - will invoke __fini destructor */
    PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

    PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;
}

```

```

CORBA_free (objid);

    CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

    CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

    /* ORB: tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
    }
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB                 orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{
Account ref = CORBA_OBJECT_NIL;

    ref = impl_Account__create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * main
 */

int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "account.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

    server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

    servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

```

```

etk_export_object_to_file (global_orb,
    servant,
    filename,
    ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

exit (0);
}

```

5.5.3. Compiling server & client

The Makefile is roughly the same as the one in the Calculator example. By now the schema should be clear and you should be able to reuse this Makefile for numerous small projects.

Example 5-21. Makefile for the Account example

```

PREFIX ?= /usr
CC = gcc
TARGETS=account-client account-server
ORBIT_IDL=orbit-idl-2
CFLAGS=-DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
    -I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
    -I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \
    -ldl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm
IDLOUT=account-common.c account-stubs.c account-skels.c account.h

all: $(IDLOUT) account-client account-server

account-server.o : account-server.c account-skelimpl.c

account-client : account-client.o account-common.o account-stubs.o
account-server : account-server.o account-common.o account-skels.o

$(IDLOUT): account.idl
    $(ORBIT_IDL) account.idl

clean:
    rm -rf *.o *~ $(IDLOUT)

distclean: clean
    rm -rf account-client account-server

```

5.6. Byte-Sequence client & server

In this more advanced example, we will see how we can set up a client exchanging byte sequences with server. The idl definition (`byteseq.idl`) covers in-, out- and inout-parameters and looks like:

Example 5-22. byteseq.idl

```
module Examples {

    module ByteSeq {
        typedef sequence<octet> Chunk;

        interface Storage {
            void set (in Chunk chunk);
            Chunk get ();
        };
    };
}
```

Then you have to generate the skeleton and stub files. In addition to these two files the ORBit IDL compiler also generates a common file and a header file. The common file implements the memory management functions and other things, useful in the client as well as in the server. The sequence to generate the C source files is rather simple. `$orbit-idl-2 --skeleton-impl byteseq.idl` generates all the files we will use in this example.

File	Usage for Client	Usage for Server
byteseq.h	readonly	readonly
byteseq-common.c	readonly	readonly
byteseq-stubs.c	readonly	-
byteseq-skels.c	-	readonly
byteseq-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with `byteseq-client.c` in following chapter.

byteseq-client.c	write the client code
byteseq-server.c	write the generic code for servant creation

5.6.1. Byte-Sequence client

Example 5-23. byteseq-client.c

```
/* byteseq-client.c hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>. */
```

```

#include <assert.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "byteseq.h"

#include "examples-toolkit.h" /* ie. etk_etk_abort_if_exception() */

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int             *argc_ptr,
            char          *argv[],
            CORBA_ORB      *orb,
            CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

```

```

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB                orb,
                 Examples_ByteSeq_Storage servant,
                 CORBA_Environment        *ev)
{
    /* releasing managed object */
    CORBA_Object_release(servant, ev);
    if (etk_raised_exception(ev)) return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev)) return;
    }
}

/**
 *
 */
static
void
client_run_set (Examples_ByteSeq_Storage servant,
                CORBA_Environment        *ev)
{
    CORBA_long LEN      = 4*1024; /* 4KB */
    CORBA_long ITER     = 10;

    CORBA_long iter     = 0;

    Examples_ByteSeq_Chunk* chunk = NULL;

    /* flood service with large chunks of byte streams */
    for (iter = 0; iter < ITER; ++iter)
    {
        CORBA_long len      = 0;
        CORBA_octet elem    = 'A';

        g_print ("+");

        chunk = ORBit_sequence_alloc (TC_CORBA_sequence_CORBA_octet,0);

        for (len = 0; len < LEN; ++len)
            ORBit_sequence_append (chunk, &elem);

        Examples_ByteSeq_Storage_set (servant, chunk, ev);
        if (etk_raised_exception(ev)) return;

        CORBA_free (chunk);
    }
}

```

```

}

 /**
 * 
 */
static
void
client_run_get (Examples_ByteSeq_Storage servant,
CORBA_Environment           *ev)
{
CORBA_long n=10;
CORBA_long i=0;

Examples_ByteSeq_Chunk* chunk = NULL;

/* increment sequence length, beginning with 0 up to 2048 */
for (i=0; i<n; ++i)
{
g_print ("--");

chunk = Examples_ByteSeq_Storage_get (servant, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (chunk);
}
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
CORBA_char *filename = "byteseq.ref";

Examples_ByteSeq_Storage servant = CORBA_OBJECT_NIL;

CORBA_Environment ev[1];
CORBA_exception_init(ev);

client_init (&argc, argv, &global_orb, ev);
etk_abort_if_exception(ev, "init failed");

g_print ("Reading service reference from file \"%s\"\n", filename);

servant = (Examples_ByteSeq_Storage)
etk_import_object_from_file (global_orb,
filename,
ev);
etk_abort_if_exception(ev, "exporting IOR failed");

client_run_set (servant, ev);
etk_abort_if_exception(ev, "client stopped");

client_run_get (servant, ev);
etk_abort_if_exception(ev, "client stopped");


```

```

client_cleanup (global_orb, servant, ev);
    etk_abort_if_exception(ev, "cleanup failed");

    exit (0);
}

```

5.6.2. Byte-Sequence server

Example 5-24. byteseq-server.c

```

/*
 * byteseq-server program. Hacked from Examples test suite
 * by Frank Rehberger <F.Rehberger@xtradyne.de>
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "byteseq.h"
#include "byteseq-skelimpl.c"

#include "examples-toolkit.h" /* provides etk_abort_if_exception() */

static CORBA_ORB           global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA   root_poa  = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.

```

```

/*static
void
server_init (int           *argc_ptr,
             char          *argv[],
             CORBA_ORB     *orb,
             PortableServer_POA *poa,
             CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
goto failed_orb;

    (*poa) = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
if (etk_raised_exception(ev))
goto failed_poamanager;

    PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB           orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */
}

```

```

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(..) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB                 orb,
PortableServer_POA   poa,
CORBA_Object        ref,
CORBA_Environment   *ev)
{
PortableServer_ObjectId *objid      = NULL;

    objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivateoin - will invoke __fini destructor */
    PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

    PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

    CORBA_free (objid);

    CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

    CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

    /* ORB: tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
    }
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
 */
static CORBA_Object
server_activate_service (CORBA_ORB                 orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{
Examples_ByteSeq_Storage ref = CORBA_OBJECT_NIL;

```

```

ref = impl_Examples_ByteSeq_Storage_create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * main
 */

int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "byteseq.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

etk_export_object_to_file (global_orb,
    servant,
    filename,
    ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

exit (0);
}

```

Example 5-25. byteseq-skelimpl.c

```

/* This is a template file generated by command */
/* orbit-idl-2 --skeleton-impl byteseq.idl */
/* User must edit this file, inserting servant */
/* specific code between markers. */

#include "byteseq.h"

/** App-specific servant structures **/


typedef struct

```

```

{
    POA_Examples_ByteSeq_Storage servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    Examples_ByteSeq_Chunk * chunk;
    /* ----- ----- end ----- */
} impl_POA_Examples_ByteSeq_Storage;

/** Implementation stub prototypes ***/

static void
impl_Examples_ByteSeq_Storage_fini(impl_POA_Examples_ByteSeq_Storage *
    servant, CORBA_Environment * ev);
static void
impl_Examples_ByteSeq_Storage_set(impl_POA_Examples_ByteSeq_Storage * servant,
    const Examples_ByteSeq_Chunk * chunk,
    CORBA_Environment * ev);

static Examples_ByteSeq_Chunk
*impl_Examples_ByteSeq_Storage_get(impl_POA_Examples_ByteSeq_Storage *
    servant, CORBA_Environment * ev);

/** epv structures **/

static PortableServer_ServantBase__epv impl_Examples_ByteSeq_Storage_base_epv
= {
    NULL, /* _private data */
    (gpointer) & impl_Examples_ByteSeq_Storage_fini, /* finalize routine */
    NULL, /* default_POA routine */
};
static POA_Examples_ByteSeq_Storage__epv impl_Examples_ByteSeq_Storage_epv = {
    NULL, /* _private */
    (gpointer) & impl_Examples_ByteSeq_Storage_set,
    (gpointer) & impl_Examples_ByteSeq_Storage_get
};

/** vepv structures **/

static POA_Examples_ByteSeq_Storage__vepv impl_Examples_ByteSeq_Storage_vepv = {
    &impl_Examples_ByteSeq_Storage_base_epv,
    &impl_Examples_ByteSeq_Storage_epv,
};

/** Stub implementations **/

static Examples_ByteSeq_Storage
impl_Examples_ByteSeq_Storage_create(PortableServer_POA poa,
    CORBA_Environment * ev)
{
    Examples_ByteSeq_Storage retval;
    impl_POA_Examples_ByteSeq_Storage *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Examples_ByteSeq_Storage, 1);
}

```

```

newservant->servant.vepv = &impl_Examples_ByteSeq_Storage_vepv;
newservant->poa =
    (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);

POA_Examples_ByteSeq_Storage__init((PortableServer_Servant) newservant,
    ev);
/* Before servant is going to be activated all
 * private attributes must be initialized. */

/* ----- init private attributes here ----- */
newservant->chunk = ORBit_sequence_alloc (TC_CORBA_sequence_CORBA_octet, 64);
/* ----- ----- end ----- ----- */

objid = PortableServer_POA_activate_object(poa, newservant, ev);
CORBA_free(objid);
retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

return retval;
}

/***
* impl_Examples_ByteSeq_Storage_fini
*
* Destructor called after servant has been deactivated finally.
* In case any operation is invoked, application is being delayed.
*/
static void
impl_Examples_ByteSeq_Storage_fini(impl_POA_Examples_ByteSeq_Storage *
    servant, CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);

    /* No further remote method calls are delegated to
     * servant and you may free your private attributes. */
    /* ----- free private attributes here ----- */
    CORBA_free (servant->chunk);
    /* ----- ----- end ----- ----- */

    POA_Examples_ByteSeq_Storage_fini((PortableServer_Servant) servant, ev);

    g_free(servant);
}

static void
impl_Examples_ByteSeq_Storage_set(impl_POA_Examples_ByteSeq_Storage * servant,
    const Examples_ByteSeq_Chunk * chunk,
    CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
    ORBit_sequence_set_size (servant->chunk, chunk->_length);

    {
        CORBA_long i=0;
        for (i = 0; i < chunk->_length; ++i)
            ORBit_sequence_index (servant->chunk, i)
                = ORBit_sequence_index (chunk, i);
    }
}

```

```

/* ----- end ----- */
}

static Examples_ByteSeq_Chunk *
impl_Examples_ByteSeq_Storage_get(impl_POA_Examples_ByteSeq_Storage * servant,
CORBA_Environment * ev)
{
    Examples_ByteSeq_Chunk *retval;

/* ----- insert method code here ----- */
    retval = ORBit_sequence_alloc (TC_CORBA_sequence_CORBA_octet,
servant->chunk->_length);

{
    CORBA_long i=0;
    for (i = 0; i < servant->chunk->_length; ++i)
        ORBit_sequence_index (retval, i)
            = ORBit_sequence_index (servant->chunk, i);
}
/* ----- end ----- */

return retval;
}

```

5.6.3. Compiling client & server

Example 5-26. Makefile

```

PREFIX ?= /usr
CC = gcc
TARGETS=byteseq-client byteseq-server
ORBIT_IDL=$(PREFIX)/bin/orbit-idl-2
CFLAGS=-g -DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
-I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
-I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \
-lidl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm \
-lORBitCosNaming-2
IDLOUT=byteseq-common.c byteseq-stubs.c byteseq-skels.c byteseq.h

all: $(IDLOUT) byteseq-client byteseq-server

byteseq-server.o: byteseq-server.c byteseq-skelimpl.c
byteseq-client : byteseq-client.o byteseq-stubs.o byteseq-common.o examples-toolkit.o
byteseq-server : byteseq-server.o byteseq-skels.o byteseq-common.o examples-toolkit.o

$(IDLOUT): byteseq.idl
$(ORBIT_IDL) byteseq.idl

%-skelimpl.c: %.idl
$(ORBIT_IDL) --skeleton-impl $^

```

```

clean:
rm -rf *.o *~ $(IDLOUT)

distclean: clean
rm -rf byteseq-client byteseq-server

```

5.7. BadCall client & server

Example 5-27. badcall.idl

```

module Examples {

interface BadCall {
struct Foo {
double fval;
};

exception NoParam      { };
exception SingleParam { string mesg; };
exception DoubleParam { string mesg; long val; };

Foo trigger (in long val, out Foo bar)
raises (NoParam, SingleParam, DoubleParam);
};

};

$ orbit-idl-2 --skeleton-impl badcall.idl  geenrates all the files we will use in this example.

```

File	Usage for Client	Usage for Server
badcall.h	readonly	readonly
badcall-common.c	readonly	readonly
badcall-stubs.c	readonly	-
badcall-skels.c	-	readonly
badcall-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with *badcall-client.c* in following chapter.

badcall-client.c	write the client code
badcall-server.c	write the generic code for servant creation

5.7.1. BadCall client

Example 5-28. badcall-client.c

```
/* badcall-client.c hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>. */

#include <assert.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "badcall.h"

#include "examples-toolkit.h" /* ie. etk_abort_if_exception() */

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int             *argc_ptr,
            char          *argv[],
            CORBA_ORB      *orb,
            CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
```

```

    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB                 orb,
                CORBA_Object            servant,
                CORBA_Environment       *ev)
{
    /* releasing managed object */
    CORBA_Object_release(servant, ev);
    if (etk_raised_exception(ev)) return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev)) return;
    }
}

static
void
client_trigger_exception (Examples_BadCall           servant,
                          CORBA_long                  arg,
                          CORBA_Environment          *ev)
{
    CORBA_long           in_arg   = arg;
    Examples_BadCall_Foo *out_arg = NULL;

    Examples_BadCall_Foo ret_val;

    ret_val = Examples_BadCall_trigger (servant,
                                         in_arg,
                                         out_arg,
                                         ev);

    switch(etk_exception_type(ev)) {
    case CORBA_NO_EXCEPTION:/* successful outcome*/

        /* now use data the server delivered to client
         * over the return-value, or those out- and
         * inout-parameters */

        break;

    case CORBA_USER_EXCEPTION:/* a user-defined exception */
}

```

```

if (etk_raised_exception_is_a (ev,
    ex_Examples_BadCall_NoParam))
{
/* NoParam exception does not own members */
Examples_BadCall_NoParam *bc
= (Examples_BadCall_NoParam*)CORBA_exception_value(ev);
g_warning ("raised exception: %s\n",
    CORBA_exception_id(ev));
}
else if (etk_raised_exception_is_a (ev,
    ex_Examples_BadCall_SingleParam))
{
Examples_BadCall_SingleParam *bc
= (Examples_BadCall_SingleParam*)
CORBA_exception_value(ev);

g_warning ("raised exception: %s\n"
    " mesg: %s\n",
    CORBA_exception_id(ev),
    bc->mesg);

} else if (etk_raised_exception_is_a
    (ev, ex_Examples_BadCall_DoubleParam))
{
Examples_BadCall_DoubleParam *bc
= (Examples_BadCall_DoubleParam*)
CORBA_exception_value(ev);

g_warning ("raised exception: %s\n"
    " mesg: %s\n",
    " val: %d\n",
    CORBA_exception_id(ev),
    bc->mesg,
    bc->val);
}
else
{
/* should never get here ... */
g_print ("unexpected CORBA_USER_EXCEPTION -%s\n",
    CORBA_exception_id(ev));
}
break;

case CORBA_SYSTEM_EXCEPTION:
default: /* standard exception */
/*
 * CORBA_exception_id() can be used to determine which
 * particular standard exception was raised; the minor
 * member of the struct associated with the exception
 * (as yielded by CORBA_exception_value()) may provide
 * additional system-specific information about the
 * exception
 */
g_print ("BadCall::trigger raised system exception: %s\n",
    CORBA_exception_id(ev));

break;

```

```

}

/* free any storage associated with exception */
CORBA_exception_free(ev);

CORBA_free (out_arg); /* free Foo data */

}

/***
 *
 */
static
void
client_run (Examples_BadCall           servant,
            CORBA_Environment      *ev)
{
CORBA_long N=1000;
CORBA_long i=0;

/* increment sequence length, beginning with 0 up to 2048 */
for (i=0; i<N; ++i)
{
  client_trigger_exception (servant, i, ev);
}
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
CORBA_char filename[] = "badcall.ref";

  Examples_BadCall servant = CORBA_OBJECT_NIL;

  CORBA_Environment ev[1];
  CORBA_exception_init(ev);

  client_init (&argc, argv, &global_orb, ev);
  etk_abort_if_exception(ev, "init failed");

  g_print ("Reading service reference from file \"%s\"\n",
filename);

  servant = etk_import_object_from_file (global_orb,
                                         filename,
                                         ev);
  etk_abort_if_exception(ev, "importing IOR failed");

  client_run (servant, ev);
  etk_abort_if_exception(ev, "client stopped");

  client_cleanup (global_orb, servant, ev);
  etk_abort_if_exception(ev, "cleanup failed");
}

```

```
    exit (0);
}
```

5.7.2. BadCall server

Example 5-29. badcall-server.c

```
/*
 * echo-server program. Hacked from Echo test suite by by Frank
 * Rehberger <F.Rehberger@xtradyne.de>
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>

#include "badcall.h"
#include "badcall-skelimpl.c"

#include "examples-toolkit.h" /* ie. etk_abort_if_exception() */

static CORBA_ORB           global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA  root_poa  = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */static
void
```

```

server_init (int             *argc_ptr,
             char            *argv[],
             CORBA_ORB       *orb,
             PortableServer_POA *poa,
             CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
goto failed_orb;

    (*poa) = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
if (etk_raised_exception(ev))
goto failed_poamanager;

    PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB           orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
}

```

```

if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(.) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB          orb,
PortableServer_POA   poa,
CORBA_Object        ref,
CORBA_Environment   *ev)
{
PortableServer_ObjectId *objid      = NULL;

objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivation - will invoke __fini destructor */
PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (objid);

CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

/* ORB: tear down the ORB */
if (orb != CORBA_OBJECT_NIL)
{
    /* going to destroy orb.. */
    CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
}
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB          orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{
Examples_BadCall ref = CORBA_OBJECT_NIL;

ref = impl_Examples_BadCall_create (poa, ev);

```

```

if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * main
*/,
int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "badcall.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

etk_export_object_to_file (global_orb,
    servant,
    filename,
    ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

exit (0);
}

```

Example 5-30. badcall-skelimpl.c

```

/* This is a template file generated by command */
/* orbit-idl-2 --skeleton-impl badcall.idl */
/* User must edit this file, inserting servant */
/* specific code between markers. */

#include "badcall.h"

/** App-specific servant structures **/


typedef struct
{
    POA_Examples_BadCall servant;

```

```

PortableServer_POA poa;

/* ----- add private attributes here ----- */
CORBA_long counter;
/* ----- ----- end ----- ----- */
} impl_POA_Examples_BadCall;

/** Implementation stub prototypes **/

static void impl_Examples_BadCall_fini(impl_POA_Examples_BadCall *
servant, CORBA_Environment * ev);

static Examples_BadCall_Foo
impl_Examples_BadCall_trigger(impl_POA_Examples_BadCall * servant,
    const CORBA_long val,
    Examples_BadCall_Foo * bar,
    CORBA_Environment * ev);

/** epv structures **/

static PortableServer_ServantBase__epv impl_Examples_BadCall_base_epv = {
    NULL, /* _private data */
    (gpointer) & impl_Examples_BadCall_fini, /* finalize routine */
    NULL, /* default_POA routine */
};
static POA_Examples_BadCall__epv impl_Examples_BadCall_epv = {
    NULL, /* _private */
    (gpointer) & impl_Examples_BadCall_trigger,
};

/** vepv structures **/

static POA_Examples_BadCall__vepv impl_Examples_BadCall_vepv = {
    &impl_Examples_BadCall_base_epv,
    &impl_Examples_BadCall_epv,
};

/** Stub implementations **/

static Examples_BadCall
impl_Examples_BadCall_create(PortableServer_POA poa, CORBA_Environment * ev)
{
    Examples_BadCall retval;
    impl_POA_Examples_BadCall *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Examples_BadCall, 1);
    newservant->servant.vepv = &impl_Examples_BadCall_vepv;
    newservant->poa =
        (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);
    POA_Examples_BadCall_init((PortableServer_Servant) newservant, ev);
    /* Before servant is going to be activated all
     * private attributes must be initialized. */

    /* ----- init private attributes here ----- */
}

```

```

newservant->counter=0; /* init */
/* ----- ----- end ----- */

objid = PortableServer_POA_activate_object(poa, newservant, ev);
CORBA_free(objid);
retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

return retval;
}

static void
impl_Examples_BadCall_fini (impl_POA_Examples_BadCall * servant,
    CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);

    /* No further remote method calls are delegated to
     * servant and you may free your private attributes. */
    /* ----- free private attributes here ----- */
    servant->counter=0; /* reset */
    /* ----- ----- end ----- */

POA_Examples_BadCall_fini((PortableServer_Servant) servant, ev);

g_free (servant);
}

static Examples_BadCall_Foo
impl_Examples_BadCall_trigger(impl_POA_Examples_BadCall * servant,
    const CORBA_long val,
    Examples_BadCall_Foo * bar,
    CORBA_Environment * ev)
{
    Examples_BadCall_Foo ret_val = {0.0};

    /* ----- insert method code here ----- */
    switch ((servant->counter++) % 2)
    {
    case 0:
    {
        /* this piece of code demonstrates how to raise exception
         * without any further parameter */

        Examples_BadCall_Foo dummy_foo = {0.0};

        /* after user has assinged exception attributes, user may
         * not touch the data anymore, ownership is handed over to
         * CORBA environment */
        CORBA_exception_set (ev,
CORBA_USER_EXCEPTION,
                                ex_Examples_BadCall_NoParam,
                                NULL); /* exception has no members */

        /* on exception you need not to care about out-argument
         * @bar, but due to programming language C it is necessary
         * to return valid value */
    }
}

```

```

        return dummy_foo;
        break;
    }
    case 1:
    {
/* this piece of code demonstrates how to raise exception
 * that has a string as parameter */

Examples_BadCall_Foo dummy_foo = {0.0};

Examples_BadCall_SingleParam* ex_parameters
= Examples_BadCall_SingleParam_alloc();

ex_parameters->mesg
= CORBA_string_dup ("raised in \" __FILE__ \"");

/* after user has assinged exception attributes, user may
 * not touch the data anymore, ownership is handed over to
 * CORBA environment */
CORBA_exception_set (ev,
CORBA_USER_EXCEPTION,
                    ex_Examples_BadCall_SingleParam,
                    ex_parameters); /* exception has members */

/* on exception you need not to care about out-argument
 * @bar, but due to programming language C it is necessary
 * to return valid value */
return dummy_foo;
break;
}
/* this code will never raise exception DoubleParam */

default:
    g_assert_not_reached ();
}
/* ----- ----- end ----- ----- */

return ret_val;
}

```

5.7.3. Compiling client & server

Example 5-31. Makefile

```

PREFIX ?= /usr
CC = gcc
TARGETS=badcall-client badcall-server
ORBIT_IDL=$(PREFIX)/bin/orbit-idl-2
CFLAGS=-g -DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
-I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
-I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \

```

```

-lidl -lgobject-2.0 -lgthread-2.0 -lpthread -lplib-2.0 -lm      \
-lORBitCosNaming-2

IDLOUT=badcall-common.c badcall-stubs.c badcall-skels.c badcall.h

all: $(IDLOUT) badcall-client badcall-server

badcall-server.o: badcall-server.c badcall-skelimpl.c

badcall-client : badcall-client.o badcall-stubs.o badcall-common.o examples-toolkit.o
badcall-server : badcall-server.o badcall-skels.o badcall-common.o examples-toolkit.o

$(IDLOUT): badcall.idl
$(ORBIT_IDL) badcall.idl

%-skelimpl.c: %.idl
$(ORBIT_IDL) --skeleton-impl $^

clean:
rm -rf *.o *~ $(IDLOUT) *.ior *.ref

distclean: clean
rm -rf badcall-client badcall-server

```

5.8. NameResolve client & server

Example 5-32. name-resolve.idl

```

module Examples {
module NameResolve {
interface Service {
void echoString (in string input);
};
};
}
;
```

\$ orbit-idl-2 --skeleton-impl name-resolve.idl generates all the files we will use in this example.

File	Usage for Client	Usage for Server
name-resolve.h	readonly	readonly
name-resolve-common.c	readonly	readonly
name-resolve-stubs.c	readonly	-
name-resolve-skels.c	-	readonly
name-resolve-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with *name-resolve-client.c* in following chapter.

name-resolve-client.c	write the client code
name-resolve-server.c	write the generic code for servant creation

5.8.1. Example- Toolkit Helpers

Example 5-33. example-toolkit.c(etk_get_name_service)

```
/** resolves default name-service, usually given to application as
 * command line argument "-ORBInitRef NameService=IOR:0100000028..",
 * or since release 2.8.0 corbalocs in form of URL can be used, eg:
 * "-ORBInitRef NameService=corbaloc:iiop:HOSTNAME:PORT/NameService%00"
 */
CosNaming_NamingContext
etk_get_name_service (CORBA_ORB                orb,
                     CORBA_Environment *ev)
{
    CORBA_char    *str=NULL;
    CORBA_Object   ref
        = (CORBA_Object) CORBA_ORB_resolve_initial_references(orb,
    "NameService",
                                         ev);
    if (etk_raised_exception(ev)) return CORBA_OBJECT_NIL;

    return (CosNaming_NamingContext) ref;
}
```

Example 5-34. example-toolkit.c(etk_name_service_bind)

```
/** calculate length of NULL terminated string vector */
static
guint
id_vec_len (char *id_vec[])
{
gint i=0;
for (i = 0; id_vec[i]; ++i);
return i;
}

/* binds @servant object reference to unique @name at
 * @name_service. @name is a NULL terminated list of strings
 * (CORBA_char*). If error occurs @ev points to exception object on
 * return.
 */
void
etk_name_service_bind (CosNaming_NamingContext  name_service,
                      CORBA_Object            servant,
                      gchar                  *id_vec[],
                      CORBA_Environment       *ev)
{
```

```

gint i = 0;
gint len = id_vec_len (id_vec);

/* Allocate a CosNaming::Name (sequence of CosNaming::NameComponent) */
CosNaming_Name *name = CosNaming_Name__alloc();

name->_buffer = CORBA_sequence_CosNaming_NameComponent_allocbuf(len);
name->_maximum = len;
name->_length = 0;

/* Relinquish ownership of the NameComponent to the
 * sequence. When CORBA_free is called on it later, the
 * NameComponent will be freed */
CORBA_sequence_set_release (name, TRUE);

/* iterate components of name and create sub-context
 * (directory) if needed */
for (i = 0; i < len; ++i) {
name->_length = i+1;
name->_buffer[i].id = CORBA_string_dup(id_vec[i]);
name->_buffer[i].kind = CORBA_string_dup("");
/* don't know what 'kind' shall be good for */

if (name->_length < len)
{
/* create a sub-context */
CosNaming_NamingContext nc =
CosNaming_NamingContext_bind_new_context (name_service,
    name,
    ev);
if (etk_raised_exception_is_a (ev,
    ex_CosNaming_NamingContext_AlreadyBound))
{
/* ignore - ctx allread exists, this
 * is not dramatic */
CORBA_exception_free (ev);
}
else if (etk_raised_exception (ev))
{
/* critical - unexpected exception */
CORBA_free (name);
return;
}
}
else
{
/* Bind object to last context - use 'rebind'
 * operation in case the name has been
 * registered allready in context - note, this
 * might interfere with other service choosing
 * same name */
CosNaming_NamingContext_rebind (name_service,
    name,
    servant,
    ev);
if (etk_raised_exception(ev)) {
/* critical - can not bind object */
}
}
}

```

```

CORBA_free (name);
return;
}
}
}

CORBA_free (name);
return;
}

```

Example 5-35. example-toolkit.c(etk_name_service_resolve)

```

/* resolves object reference @return with unique @name at
 * @name_service. @name is a NULL terminated list of strings
 * (CORBA_char*). If error occurs @ev points to * exception object
 * on return.
 */
CORBA_Object
etk_name_service_resolve (CosNaming_NamingContext name_service,
    gchar           *id_vec[],
    CORBA_Environment   *ev)
{
CORBA_Object retval = CORBA_OBJECT_NIL;
gint i = 0;
gint len = id_vec_len (id_vec);

/* Allocate a CosNaming::Name (sequence of CosNaming::NameComponent) */
CosNaming_Name *name = CosNaming_Name__alloc();

g_assert (id_vec_len (id_vec) > 0);

name->_buffer = CORBA_sequence_CosNaming_NameComponent_allocbuf(len);
name->_maximum = len;
name->_length  = 0;

/* Relinquish ownership of the NameComponent to the
 * sequence. When CORBA_free is called on it later, the
 * NameComponent will be freed */
CORBA_sequence_set_release (name, TRUE);

/* iterate components of name and create sub-context
 * (directory) if needed */
for (i = 0; i < len; ++i) {
name->_length = i+1;
name->_buffer[i].id  = CORBA_string_dup(id_vec[i]);
name->_buffer[i].kind = CORBA_string_dup("");
/* don't know what 'kind' shall be good for */
}

retval = CosNaming_NamingContext_resolve (name_service,
    name,
    ev);

if (etk_raised_exception (ev)) {
CORBA_free (name);
return CORBA_OBJECT_NIL;
}

```

```
return retval;
}
```

5.8.2. NameResolve client

Example 5-36. name-resolve-client.c

```
/*
 * Name-Resolve client program.. Hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>
 *
 * Client connects to name-service and resolves object reference from server and
 * forwards console input to name-resolve-server. A dot . as single character
 * in input terminates the client.
 */

#include <stdio.h>
#include <signal.h>
#include <orbit/orbit.h>

/*
 * This header file was generated from the idl
 */

#include "name-resolve.h"
#include "examples-toolkit.h" /* provides etk_abort_if_exception */

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call

```

```

* echo_client_shutdown function in case of SIGINT and SIGTERM
* signals. If error occurs @ev points to exception object on
* return.
*/
static
void
client_init (int           *argc_ptr,
             char          *argv[],
             CORBA_ORB      *orb,
             CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT, client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB           orb,
                CORBA_Object        service,
                CORBA_Environment   *ev)
{
    /* releasing managed object */
    CORBA_Object_release(service, ev);
    if (etk_raised_exception(ev)) return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev)) return;
    }
}

/**
 *
 */
static
void
client_run (Examples_NameResolve_Service  service,
            CORBA_Environment          *ev)
{
char filebuffer[1024+1];

g_print("Type any text to console to be sent to server,\n"
       "a single dot in line will terminate input\n");

```

```

while( fgets(filebuffer,1024,stdin) ) {
if( filebuffer[0] == '.' && filebuffer[1] == '\n' )
break;

/* chop the newline off */
filebuffer[strlen(filebuffer)-1] = '\0';

/* using the echoString method in the Echo object
 * this is defined in the echo.h header, compiled from
 * echo.idl */

Examples_NameResolve_Service_echoString (service,
filebuffer,
ev);
if (etk_raised_exception (ev)) return;
}
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
Examples_NameResolve_Service service = CORBA_OBJECT_NIL;
CosNaming_NamingContext name_service = CORBA_OBJECT_NIL;

gchar *id[] = {"Examples", "NameResolve", "Service", NULL};

    CORBA_Environment ev[1];
    CORBA_exception_init(ev);

client_init (&argc, argv, &global_orb, ev);
etk_abort_if_exception(ev, "init failed");

g_print ("Resolving service reference from name-service with id \"%s/%s/%s\"\n", id[0], id[1], id[2]);

name_service = etk_get_name_service (global_orb, ev);
etk_abort_if_exception(ev, "failed resolving name-service");

service
    = (Examples_NameResolve_Service)
etk_name_service_resolve (name_service, id, ev);
etk_abort_if_exception(ev, "failed resolving service at name-service");

client_run (service, ev);
    etk_abort_if_exception(ev, "service not reachable");

client_cleanup (global_orb, service, ev);
    etk_abort_if_exception(ev, "cleanup failed");

    exit (0);
}

```

5.8.3. NameResolve server

Example 5-37. name-resolve-server.c

```

/*
 * echo-server program. Hacked from Echo test suite by
 * <birney@sanger.ac.uk>, ORBit2 update by Frank Rehberger
 * <F.Rehberger@xtradyne.de>
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <corbit/orbit.h>

#include "name-resolve-skelimpl.c"
#include "examples-toolkit.h" /* provides etk_abort_if_exception */

static CORBA_ORB          global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA root_poa   = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */static
void
server_init (int             *argc_ptr,
            char           *argv[],
            CORBA_ORB      *orb,
            PortableServer_POA *poa,
            CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

```

```

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
goto failed_orb;

    (*poa) = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
if (etk_raised_exception(ev))
goto failed_poamanager;

PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB             orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(.) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.

```

```

/*
static void
server_cleanup (CORBA_ORB          orb,
PortableServer_POA   poa,
CORBA_Object        ref,
CORBA_Environment   *ev)
{
PortableServer_ObjectId *objid      = NULL;

objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivation - will invoke __fini destructor */
PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (objid);

CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

/* ORB: tear down the ORB */
if (orb != CORBA_OBJECT_NIL)
{
    /* going to destroy orb.. */
    CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
}
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB          orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{
Examples_NameResolve_Service ref = CORBA_OBJECT_NIL;

ref = impl_Examples_NameResolve_Service__create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
* main

```

```

*/
```

```

int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;
CosNaming_NamingContext name_service = CORBA_OBJECT_NIL;

gchar *id[] = {"Examples", "NameResolve", "Service", NULL};

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Binding service reference at name service against id: %s/%s/%s\n\n", id[0], id[1], id[2]);

name_service = etk_get_name_service (global_orb, ev);
etk_abort_if_exception(ev, "failed resolving name-service");

etk_name_service_bind (name_service, servant, id, ev);
etk_abort_if_exception(ev, "failed binding of service");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

exit (0);
}

```

Example 5-38. name-resolve-skelimpl.c

```

/* This is a template file generated by command */
/* orbit-idl-2 --skeleton-impl name-resolve.idl */
/* User must edit this file, inserting servant */
/* specific code between markers. */

#include "name-resolve.h"

/*** App-specific servant structures ***/

typedef struct
{
    POA_Examples_NameResolve_Service servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    /* ----- ----- end ----- */
} impl_POA_Examples_NameResolve_Service;

```

```

/** Implementation stub prototypes ***/

static void
impl_Examples_NameResolve_Service__fini(impl_POA_Examples_NameResolve_Service
* servant, CORBA_Environment * ev);
static void
impl_Examples_NameResolve_Service_echoString
(impl_POA_Examples_NameResolve_Service * servant, const CORBA_char * input,
CORBA_Environment * ev);

/** epv structures **/

static PortableServer_ServantBase__epv
impl_Examples_NameResolve_Service_base_epv = {
NULL, /* _private data */
(gpointer) & impl_Examples_NameResolve_Service__fini, /* finalize routine */
NULL, /* default_POA routine */
};
static POA_Examples_NameResolve_Service__epv
impl_Examples_NameResolve_Service_epv = {
NULL, /* _private */
(gpointer) & impl_Examples_NameResolve_Service_echoString,
};

/** vepv structures **/

static POA_Examples_NameResolve_Service__vepv
impl_Examples_NameResolve_Service_vepv = {
&impl_Examples_NameResolve_Service_base_epv,
&impl_Examples_NameResolve_Service_epv,
};

/** Stub implementations **/

static Examples_NameResolve_Service
impl_Examples_NameResolve_Service__create(PortableServer_POA poa,
CORBA_Environment * ev)
{
    Examples_NameResolve_Service retval;
    impl_POA_Examples_NameResolve_Service *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Examples_NameResolve_Service, 1);
    newservant->servant.vepv = &impl_Examples_NameResolve_Service_vepv;
    newservant->poa =
        (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);

    POA_Examples_NameResolve_Service__init((PortableServer_Servant) newservant,
ev);
    /* Before servant is going to be activated all
     * private attributes must be initialized. */

    /* ----- init private attributes here ----- */
    /* ----- ----- end ----- ----- */
}

```

```

objid = PortableServer_POA_activate_object(poa, newservant, ev);
CORBA_free(objid);
retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

return retval;
}

/***
* impl_Examples_NameResolve_Service__fini
*
* Destructor called after servant has been deactivated finally.
* In case any active operation invocation, method call is being delayed.
* Note, in former versions of ORBit2 this function would have been
* named impl_Examples_NameResolve_Service__destroy.
*/
static void
impl_Examples_NameResolve_Service__fini(impl_POA_Examples_NameResolve_Service
* servant, CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);

    /* No further remote method calls are delegated to
     * servant and you may free your private attributes. */
    /* ----- free private attributes here ----- */
    /* ----- ----- end ----- */

    POA_Examples_NameResolve_Service__fini((PortableServer_Servant) servant,
    ev);

    g_free(servant);
}

static void
impl_Examples_NameResolve_Service_echoString
(impl_POA_Examples_NameResolve_Service * servant, const CORBA_char * input,
 CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
    g_print (">> %s\n", input);
    /* ----- ----- end ----- */
}

```

5.8.4. Compiling client & server

Example 5-39. Makefile

```

PREFIX ?= /usr
CC = gcc
TARGETS=name-resolve-client name-resolve-server
ORBIT_IDL=$(PREFIX)/bin/orbit-idl-2
CFLAGS=-DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
      -I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \

```

```

-I$(PREFIX)/lib/glib-2.0/include -g
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \
-lldl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm           \
-lORBitCosNaming-2
IDLOUT=name-resolve-common.c name-resolve-stubs.c name-resolve-skels.c name-resolve.h
all: $(IDLOUT) name-resolve-client name-resolve-server

name-resolve-server.o: name-resolve-server.c name-resolve-skelimpl.c

name-resolve-client : name-resolve-client.o name-resolve-stubs.o name-resolve-common.o examples-t
name-resolve-server : name-resolve-server.o name-resolve-skels.o name-resolve-common.o examples-t

$(IDLOUT): name-resolve.idl
$(ORBIT_IDL) name-resolve.idl

%-skelimpl.c: %.idl
$(ORBIT_IDL) --skeleton-impl $^

clean:
rm -rf *.o *~ $(IDLOUT) *.ior *.ref

distclean: clean
rm -rf name-resolve-client name-resolve-server

```

5.9. Factory client & server

Example 5-40. factory.idl

```

module Examples {

module Factory {

interface AbstractService {
void doit (in string mesg);
void destroy ();
};

interface Producer {
AbstractService produce (in string id);
};

};

$ orbit-idl-2 --skeleton-impl factory.idl  geenrates all the files we will use in this example.

```

File	Usage for Client	Usage for Server
factory.h	readonly	readonly
factory-common.c	readonly	readonly

File	Usage for Client	Usage for Server
factory-stubs.c	readonly	-
factory-skels.c	-	readonly
factory-skelimpl.c	-	template for user code

Files remaining to write are listed in following table, starting with *factory-client.c* in following chapter.

factory-client.c	write the client code
factory-server.c	write the generic code for servant creation

5.9.1. Factory client

Example 5-41. factory-client.c

```
/* factory-client.c hacked by Frank Rehberger
 * <F.Rehberger@xtradyne.de>.  */

#include <assert.h>
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <unistd.h>
#include <orbit/orbit.h>

#include "examples-toolkit.h" /* etk_ functions */
#include "factory.h"

static CORBA_ORB  global_orb = CORBA_OBJECT_NIL; /* global orb */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
client_shutdown (int sig)
{
    CORBA_Environment  local_ev[1];
    CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}
```

```

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_client_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
client_init (int             argc_ptr,
             char          *argv[],
             CORBA_ORB     *orb,
             CORBA_Environment *ev)
{
    /* init signal handling */

    signal(SIGINT,  client_shutdown);
    signal(SIGTERM, client_shutdown);

    /* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
    if (etk_raised_exception(ev)) return;
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static
void
client_cleanup (CORBA_ORB           orb,
                CORBA_Object        servant,
                CORBA_Environment   *ev)
{
    /* releasing managed object */
    CORBA_Object_release(servant, ev);
    if (etk_raised_exception(ev))
return;

    /* tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */
        CORBA_ORB_destroy(orb, ev);
        if (etk_raised_exception(ev))
return;
    }
}

/***
 *
 */
static
void
client_run (Examples_Factory_Producer      factory,
            CORBA_Environment           *ev)
{

```

```

#define MAX_ID_LEN 100

CORBA_char service_id [MAX_ID_LEN+1] = "";
gint i = 0;
gint j = 0;

for (i = 0; i<20; ++i)
{
snprintf (service_id, MAX_ID_LEN, "id-%d", i);

g_printf ("abstract-service: create,");
Examples_Factory_AbstractService service
= Examples_Factory_Producer_produce (factory,
    service_id,
    ev);
if (etk_raised_exception (ev))
return;

for (j = 0; j < 5; ++j)
{
g_printf (" apply,");

CORBA_char *mesg = "hallo welt";
Examples_Factory_AbstractService_doit (service,
    mesg,
    ev);
if (etk_raised_exception (ev))
return;
}

g_printf (" destroy\n");

Examples_Factory_AbstractService_destroy (service, ev);
if (etk_raised_exception (ev))
return;

CORBA_Object_release ((CORBA_Object) service, ev);
if (etk_raised_exception (ev))
return;

}
#endif MAX_IDL_LEN
}

/*
 * main
 */
int
main(int argc, char* argv[])
{
    CORBA_char filename[] = "factory.ref";

    Examples_Factory_Producer producer = CORBA_OBJECT_NIL;

    CORBA_Environment ev[1];
    CORBA_exception_init(ev);

```

```

client_init (&argc, argv, &global_orb, ev);
etk_abort_if_exception(ev, "init failed");

g_print ("Reading service reference from file \"%s\"\n", filename);

producer
= (Examples_Factory_Producer)
etk_import_object_from_file (global_orb,
filename,
ev);
etk_abort_if_exception(ev, "import service failed");

client_run (producer, ev);
etk_abort_if_exception(ev, "service not reachable");

client_cleanup (global_orb, producer, ev);
etk_abort_if_exception(ev, "cleanup failed");

exit (0);
}

```

5.9.2. Factory server

Example 5-42. factory-server.c

```

/*
 * factory-server program. Hacked by Frank
 * Rehberger <F.Rehberger@extradyne.de>
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <orbit/orbit.h>
#include <ORBit/services/CosNaming.h>

#include "factory.h"
#include "factory-skelimpl.c"

#include "examples-toolkit.h" /* etk_ functions */

static CORBA_ORB global_orb = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA root_poa = CORBA_OBJECT_NIL; /* root POA

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{

```

```

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/* Inits ORB @orb using @argv arguments for configuration. For each
 * ORBit options consumed from vector @argv the counter of @argc_ptr
 * will be decremented. Signal handler is set to call
 * echo_server_shutdown function in case of SIGINT and SIGTERM
 * signals. If error occurs @ev points to exception object on
 * return.
 */
static
void
server_init (int             *argc_ptr,
             char            *argv[],
             CORBA_ORB       *orb,
             PortableServer_POA *poa,
             CORBA_Environment *ev)
{
PortableServer_POAManager poa_manager = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGINT, server_shutdown);
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
    goto failed_orb;

    (*poa) = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
    goto failed_poa;

    poa_manager = PortableServer_POA_get_the_POAManager(*poa, ev);
if (etk_raised_exception(ev))
    goto failed_poamanager;

PortableServer_POAManager_activate(poa_manager, ev);
if (etk_raised_exception(ev))
    goto failed_activation;

    CORBA_Object_release ((CORBA_Object) poa_manager, ev);
return;

failed_activation:
failed_poamanager:

```

```

    CORBA_Object_release ((CORBA_Object) poa_manager, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB             orb,
            CORBA_Environment *ev)
{
    /* enter main loop until SIGINT or SIGTERM */

    CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

    /* user pressed SIGINT or SIGTERM and in signal handler
     * CORBA_ORB_shutdown(..) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB             orb,
                PortableServer_POA poa,
                CORBA_Object       ref,
                CORBA_Environment *ev)
{
PortableServer_ObjectId *objid = NULL;

objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivation - will invoke __fini destructor */
PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (objid);

    CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

    CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

    /* ORB: tear down the ORB */
    if (orb != CORBA_OBJECT_NIL)
    {
        /* going to destroy orb.. */

```

```

        CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
    }
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
*/
static CORBA_Object
server_activate_service (CORBA_ORB           orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{
Examples_Factory_Producer ref = CORBA_OBJECT_NIL;

ref = impl_Examples_Factory_Producer__create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * main
*/
int
main (int argc, char *argv[])
{
CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "factory.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &root_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

servant = server_activate_service (global_orb, root_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

etk_export_object_to_file (global_orb,
    servant,
    filename,
    ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, root_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");
}

```

```
exit (0);
}
```

Example 5-43. factory-skelimpl.c

```
/*
 * This is a template file generated by command
 * orbit-idl-2 --skeleton-impl name-resolve.idl
 * User must edit this file, inserting servant
 * specific code between markers.
 */

#include "factory.h"

/** App-specific servant structures **/

typedef struct
{
    POA_Examples_Factory_AbstractService servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    CORBA_char *id;
    CORBA_long counter;
    /* ----- ----- end ----- ----- */
} impl_POA_Examples_Factory_AbstractService;

typedef struct
{
    POA_Examples_Factory_Producer servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    /* ----- ----- end ----- ----- */
} impl_POA_Examples_Factory_Producer;

/** Implementation stub prototypes **/

static void
impl_Examples_Factory_AbstractService_fini
(impl_POA_Examples_Factory_AbstractService * servant,
 CORBA_Environment * ev);
static void
impl_Examples_Factory_AbstractService_doit
(impl_POA_Examples_Factory_AbstractService * servant,
 const CORBA_char * mesg, CORBA_Environment * ev);

static void
impl_Examples_Factory_AbstractService_destroy
(impl_POA_Examples_Factory_AbstractService * servant,
 CORBA_Environment * ev);

static void
impl_Examples_Factory_Producer_fini
(impl_POA_Examples_Factory_Producer * servant, CORBA_Environment * ev);
static Examples_Factory_AbstractService
```

```

impl_Examples_Factory_Producer_produce
(impl_POA_Examples_Factory_Producer * servant, const CORBA_char * id,
 CORBA_Environment * ev);

/*** epv structures ***/
static PortableServer_ServantBase__epv
impl_Examples_Factory_AbstractService_base_epv = {
NULL, /* _private data */
(gpointer) & impl_Examples_Factory_AbstractService_fini, /* finalize routine */
NULL, /* default_POA routine */
};

static POA_Examples_Factory_AbstractService__epv
impl_Examples_Factory_AbstractService_epv = {
NULL, /* _private */
(gpointer) & impl_Examples_Factory_AbstractService_doit,
(gpointer) & impl_Examples_Factory_AbstractService_destroy,
};

static PortableServer_ServantBase__epv
impl_Examples_Factory_Producer_base_epv = {
NULL, /* _private data */
(gpointer) & impl_Examples_Factory_Producer_fini, /* finalize routine */
NULL, /* default_POA routine */
};

static POA_Examples_Factory_Producer__epv impl_Examples_Factory_Producer_epv = {
NULL, /* _private */
(gpointer) & impl_Examples_Factory_Producer_produce,
};

/*** vepv structures ***/
static POA_Examples_Factory_AbstractService__vepv
impl_Examples_Factory_AbstractService_vepv = {
&impl_Examples_Factory_AbstractService_base_epv,
&impl_Examples_Factory_AbstractService_epv,
};

static POA_Examples_Factory_Producer__vepv
impl_Examples_Factory_Producer_vepv = {
&impl_Examples_Factory_Producer_base_epv,
&impl_Examples_Factory_Producer_epv,
};

/*** Stub implementations ***/
static Examples_Factory_AbstractService
impl_Examples_Factory_AbstractService__create (PortableServer_POA poa,
                                              const CORBA_char * id,
                                              CORBA_Environment * ev)
{
    Examples_Factory_AbstractService retval;
    impl_POA_Examples_Factory_AbstractService *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0 (impl_POA_Examples_Factory_AbstractService, 1);
}

```

```

newservant->servant.vepv = &impl_Examples_AbstractService_vepv;
newservant->poa =
    (PortableServer_POA) CORBA_Object_duplicate ((CORBA_Object) poa, ev);
POA_Examples_AbstractService__init ((PortableServer_Servant)
    newservant, ev);
/*
 * Before servant is going to be activated all private attributes must
 * be initialized.
 */
/* ----- init private attributes here ----- */
newservant->id = CORBA_string_dup (id);
newservant->counter = 0;
/* ----- ----- end ----- */

objid = PortableServer_POA_activate_object (poa, newservant, ev);
CORBA_free (objid);
retval = PortableServer_POA_servant_to_reference (poa, newservant, ev);

return retval;
}

/***
* impl_Examples_AbstractService_fini
*
* Destructor called after servant has been deactivated finally.
* In case any operation invocation, method invocation is being delayed.
* Note, in former versions of ORBIT2 this function would have been
* named impl_Examples_AbstractService_destroy.
*/
static void
impl_Examples_AbstractService_fini
(impl_POA_Examples_AbstractService * servant,
 CORBA_Environment * ev)
{
    CORBA_Object_release ((CORBA_Object) servant->poa, ev);

    /*
     * No further remote method calls are delegated to servant and you
     * may free your private attributes.
     */
    /* ----- free private attributes here ----- */
    CORBA_free (servant->id);
    /* ----- ----- end ----- */

    POA_Examples_AbstractService_fini ((PortableServer_Servant)
        servant, ev);

    g_free (servant);
}

static void
impl_Examples_AbstractService_doit
(impl_POA_Examples_AbstractService * servant,
 const CORBA_char * mesg, CORBA_Environment * ev)
{
    /* ----- insert method code here ----- */
}

```

```

g_print ("service-id=\"%s\", nth-call=\"%d\", \n",
servant->id,
servant->counter);
++(servant->counter);
/* ----- end ----- */
}

static void
deactivate_servant (PortableServer_POA poa,
PortableServer_Servant servant, CORBA_Environment * ev)
{
PortableServer_ObjectId *id
= PortableServer_POA_servant_to_id (poa, servant, ev);

if (etk_raised_exception (ev))
return;

PortableServer_POA_deactivate_object (poa, id, ev);

/* free id in any case */
g_free (id);
}

static void
impl_Examples_Factory_AbstractService_destroy
(impl_POA_Examples_Factory_AbstractService * servant,
CORBA_Environment * ev)
{
/* ----- insert method code here ----- */
deactivate_servant (servant->poa, servant, ev);
/* ----- end ----- */
}

static Examples_Factory_Producer
impl_Examples_Factory_Producer__create (PortableServer_POA poa,
CORBA_Environment * ev)
{
Examples_Factory_Producer retval;
impl_POA_Examples_Factory_Producer *newservant;
PortableServer_ObjectId *objid;

newservant = g_new0 (impl_POA_Examples_Factory_Producer, 1);
newservant->servant.vepv = &impl_Examples_Factory_Producer_vepv;
newservant->poa =
(PortableServer_POA) CORBA_Object_duplicate ((CORBA_Object) poa, ev);
POA_Examples_Factory_Producer__init ((PortableServer_Servant)
newservant, ev);
/*
* Before servant is going to be activated all private attributes must
* be initialized.
*/
/* ----- init private attributes here ----- */
/* ----- end ----- */

objid = PortableServer_POA_activate_object (poa, newservant, ev);
}

```

```

CORBA_free (objid);
retval = PortableServer_POA_servant_to_reference (poa, newservant, ev);

return retval;
}

/***
* impl_Examples_Factory_Producer__fini
*
* Destructor called after servant has been deactivated finally.
* In case any operation invocation, method invocation is being delayed.
* Note, in former versions of ORBIT2 this function would have been
* named impl_Exampels_Factory_Producer__destroy
*/
static void
impl_Examples_Factory_Producer__fini
(impl_POA_Examples_Factory_Producer * servant, CORBA_Environment * ev)
{
    CORBA_Object_release ((CORBA_Object) servant->poa, ev);

    /*
     * No further remote method calls are delegated to servant and you
     * may free your private attributes.
     */
    /* ----- free private attributes here ----- */
    /* ----- ----- end ----- */
}

POA_Examples_Factory_Producer__fini ((PortableServer_Servant) servant, ev);

g_free (servant);
}

static Examples_Factory_AbstractService
impl_Examples_Factory_Producer_produce
(impl_POA_Examples_Factory_Producer * servant, const CORBA_char * id,
 CORBA_Environment * ev)
{
    Examples_Factory_AbstractService retval;

    /* ----- insert method code here ----- */
    retval =
        impl_Examples_Factory_AbstractService__create (servant->poa, id, ev);
    if (etk_raised_exception (ev))
    {
        retval = CORBA_OBJECT_NIL;
    }
    /* ----- ----- end ----- */
}

return retval;
}

```

5.9.3. Compiling client & server

Example 5-44. Makefile

```
PREFIX ?= /usr
CC = gcc
TARGETS=factory-client factory-server
ORBIT_IDL=$(PREFIX)/bin/orbit-idl-2
CFLAGS=-g -DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
-I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
-I$(PREFIX)/lib/glib-2.0/include
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBCosNaming-2 -lORBit-2 -llinc -lgmodule-2.0 \
-lldl -lgobject-2.0 -lgthread-2.0 -lpthread -lplib-2.0 -lm
IDLOUT=factory-common.c factory-stubs.c factory-skels.c factory.h

all: $(IDLOUT) factory-client factory-server

factory-server.o: factory-server.c factory-skelimpl.c

factory-client : factory-client.o factory-stubs.o factory-common.o examples-toolkit.o
factory-server : factory-server.o factory-skels.o factory-common.o examples-toolkit.o

$(IDLOUT): factory.idl
$(ORBIT_IDL) factory.idl

%-skelimpl.c: %.idl
$(ORBIT_IDL) --skeleton-impl $^

clean:
rm -rf *.o *~ $(IDLOUT) *.ior *.ref

distclean: clean
rm -rf factory-client factory-server
```

5.10. Threaded calculator server

Lets take the calculator-server from previous chapter to demonstrate ORBit2 in multi threaded environment.

Example 5-45.

```
// 
// Calculator interface
//

interface Calculator
{
    double add(in double number1, in double number2);
    double sub(in double number1, in double number2);
};
```

5.10.1. multi-threaded calculator server

Example 5-46. mt-calculator-server.c

```
/*
 * calculator-server program. Hacked from Frank Rehberger
 * <F.Rehberger@xtradyne.de>.
 */

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <corbit/orbit.h>

#include "calculator.h"
#include "calculator-skelimpl.c"

#include "examples-toolkit.h"

static CORBA_ORB          global_orb  = CORBA_OBJECT_NIL; /* global orb */
static PortableServer_POA default_poa = CORBA_OBJECT_NIL; /* default POA */

/* Is called in case of process signals. it invokes CORBA_ORB_shutdown()
 * function, which will terminate the processes main loop.
 */
static
void
server_shutdown (int sig)
{
CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

    if (global_orb != CORBA_OBJECT_NIL)
    {
        CORBA_ORB_shutdown (global_orb, FALSE, local_ev);
        etk_abort_if_exception (local_ev, "caught exception");
    }
}

/**/

PortableServer_POA
server_create_multi_threaded_poa (CORBA_ORB
                                  poa,
                                  PortableServer_POAManager poa_mngr,
                                  CORBA_Environment       *ev)
{
const static      MAX_POLICIES  = 1;
PortableServer_POA child_poa     = CORBA_OBJECT_NIL;
CORBA_PolicyList *poa_policies;
```

```

poa_policies      = CORBA_PolicyList__alloc ();
poa_policies->_maximum = MAX_POLICIES;
poa_policies->_length  = MAX_POLICIES;
poa_policies->_buffer  = CORBA_PolicyList__allocbuf (MAX_POLICIES);
CORBA_sequence_set_release (poa_policies, CORBA_TRUE);

    poa_policies->_buffer[0] = (CORBA_Policy)
PortableServer_POA_create_thread_policy (
poa,
PortableServer_ORB_CTRL_MODEL,
ev);

child_poa = PortableServer_POA_create_POA (poa,
                                             "Thread Per Request POA",
                                             poa_mgr,
                                             poa_policies,
                                             ev);

if (etk_raised_exception(ev))
goto failed_create_poa;

ORBit_ObjectAdaptor_set_thread_hint ((ORBit_ObjectAdaptor) child_poa,
                                     ORBIT_THREAD_HINT_PER_REQUEST);

    CORBA_Policy_destroy (poa_policies->_buffer[0], ev);
if (etk_raised_exception(ev))
goto failed;
    CORBA_free (poa_policies);

return child_poa;

failed_create_poa:
/* FIXME, in case of error, ev is set, but destructor should not
 * return except anyway */
    CORBA_Policy_destroy (poa_policies->_buffer[0], ev);
    CORBA_free (poa_policies);
failed:
return CORBA_OBJECT_NIL;
}

/*
* Inits ORB @orb using @argv arguments for configuration. For each
* ORBit options consumed from vector @argv the counter of @argc_ptr
* will be decremented. Signal handler is set to call
* echo_server_shutdown function in case of SIGINT and SIGTERM
* signals. If error occurs @ev points to exception object on
* return.
*/
static
void
server_init (int             *argc_ptr,
            char           *argv[],
            CORBA_ORB       *orb,
            PortableServer_POA *poa,
            CORBA_Environment *ev)
{
PortableServer_POA      rootpoa      = CORBA_OBJECT_NIL;

```

```

PortableServer_POAManager rootpoa_mgr = CORBA_OBJECT_NIL;

CORBA_Environment local_ev[1];
CORBA_exception_init(local_ev);

/* init signal handling */
signal(SIGTERM, server_shutdown);

/* create Object Request Broker (ORB) */

    (*orb) = CORBA_ORB_init(argc_ptr, argv, "orbit-local-mt-orb", ev);
if (etk_raised_exception(ev))
goto failed_orb;

    rootpoa = (PortableServer_POA)
CORBA_ORB_resolve_initial_references(*orb, "RootPOA", ev);
if (etk_raised_exception(ev))
goto failed_poa;

    rootpoa_mgr = PortableServer_POA_get_the_POAManager(rootpoa, ev);
if (etk_raised_exception(ev))
goto failed_poamanager;

/* create default POA with specific policies */

(*poa) = server_create_multi_threaded_poa (*orb,
    rootpoa,
    rootpoa_mgr,
    ev);
if (etk_raised_exception(ev))
goto failed_child_poa;

PortableServer_POAManager_activate(rootpoa_mgr, ev);
if (etk_raised_exception(ev))
goto failed_activation;

    CORBA_Object_release ((CORBA_Object) rootpoa_mgr, ev);
return;

failed_activation:
failed_child_poa:
failed_poamanager:
    CORBA_Object_release ((CORBA_Object) rootpoa_mgr, local_ev);
failed_poa:
CORBA_ORB_destroy(*orb, local_ev);
failed_orb:
return;
}

/* Entering main loop @orb handles incoming request and delegates to
 * servants. If error occurs @ev points to exception object on
 * return.
 */
static void
server_run (CORBA_ORB             orb,
            CORBA_Environment *ev)
{

```

```

/* enter main loop until SIGINT or SIGTERM */

CORBA_ORB_run(orb, ev);
if (etk_raised_exception(ev)) return;

/* user pressed SIGINT or SIGTERM and in signal handler
 * CORBA_ORB_shutdown(.) has been called */
}

/* Releases @servant object and finally destroys @orb. If error
 * occurs @ev points to exception object on return.
 */
static void
server_cleanup (CORBA_ORB           orb,
PortableServer_POA   poa,
CORBA_Object        ref,
CORBA_Environment   *ev)
{
PortableServer_ObjectId *objid      = NULL;

objid = PortableServer_POA_reference_to_id (poa, ref, ev);
if (etk_raised_exception(ev)) return;

/* Servant: deactivateoin - will invoke __fini destructor */
PortableServer_POA_deactivate_object (poa, objid, ev);
if (etk_raised_exception(ev)) return;

PortableServer_POA_destroy (poa, TRUE, FALSE, ev);
if (etk_raised_exception(ev)) return;

CORBA_free (objid);

CORBA_Object_release ((CORBA_Object) poa, ev);
if (etk_raised_exception(ev)) return;

CORBA_Object_release (ref, ev);
if (etk_raised_exception(ev)) return;

/* ORB: tear down the ORB */
if (orb != CORBA_OBJECT_NIL)
{
    /* going to destroy orb.. */
    CORBA_ORB_destroy(orb, ev);
if (etk_raised_exception(ev)) return;
}
}

/* Creates servant and registers in context of ORB @orb. The ORB will
 * delegate incoming requests to specific servant object. @return
 * object reference. If error occurs @ev points to exception object
 * on return.
 */
static CORBA_Object
server_activate_service (CORBA_ORB           orb,
PortableServer_POA   poa,
CORBA_Environment   *ev)
{

```

```

Calculator ref = CORBA_OBJECT_NIL;

ref = impl_Calculator_create (poa, ev);
if (etk_raised_exception(ev))
return CORBA_OBJECT_NIL;

return ref;
}

/*
 * background task
 */
typedef struct {
int argc;
char **argv;
} BackgroundData;

static gpointer
server_in_background (BackgroundData *data)
{
int argc = data->argc;
char **argv = data->argv;

CORBA_Object servant = CORBA_OBJECT_NIL;

CORBA_char filename[] = "calculator.ref";

CORBA_Environment ev[1];
CORBA_exception_init(ev);

server_init (&argc, argv, &global_orb, &default_poa, ev);
etk_abort_if_exception(ev, "failed ORB init");

servant = server_activate_service (global_orb, default_poa, ev);
etk_abort_if_exception(ev, "failed activating service");

g_print ("Writing service reference to: %s\n\n", filename);

etk_export_object_to_file (global_orb,
servant,
filename,
ev);
etk_abort_if_exception(ev, "failed exporting IOR");

server_run (global_orb, ev);
etk_abort_if_exception(ev, "failed entering main loop");

server_cleanup (global_orb, default_poa, servant, ev);
etk_abort_if_exception(ev, "failed cleanup");

g_thread_exit (NULL);
}

static
void
main_shutdown (int sig)
{

```

```

/* progate SIGTERM signal to every process/thread in process
 * group */
kill (0, 15);

/* terminate main thread */
exit (0);
}

/*
 * main
 */
int
main (int argc, char *argv[])
{
BackgroundData data[1];
gint      i      = 0;
GError   *err    = NULL;
GThread  *thread = NULL;

g_thread_init (NULL);

data->argc = argc;
data->argv = argv;

thread = g_thread_create ((GThreadFunc) server_in_background,
  data,
  TRUE,   /*joinable */
  &err);

/* init signal handling */
signal(SIGINT,  main_shutdown);
signal(SIGHUP,  main_shutdown);

/* concurrent main task */
while (i++ < 1000) {
g_print ("main thread active\n");
sleep (1);
}

g_print ("main thread waiting for background task\n");
g_thread_join (thread);

exit (0);
}

```

In this case calculator-skelimpl.c file can be kept as before, no changes are necessary. But if servants would share common resource, it would be necessary to protect critical code sections with mutexes (locks).

Example 5-47. calculator-skelimpl.c

```

#include "calculator.h"

/** App-specific servant structures **/


typedef struct

```

```

{
    POA_Calculator servant;
    PortableServer_POA poa;

    /* ----- add private attributes here ----- */
    /* ----- ----- end ----- */
}
impl_POA_Calculator;

/* *** Implementation stub prototypes ***

static void impl_Calculator_fini (impl_POA_Calculator * servant,
    CORBA_Environment * ev);
static CORBA_double
impl_Calculator_add(impl_POA_Calculator * servant,
    const CORBA_double number1,
    const CORBA_double number2, CORBA_Environment * ev);

static CORBA_double
impl_Calculator_sub(impl_POA_Calculator * servant,
    const CORBA_double number1,
    const CORBA_double number2, CORBA_Environment * ev);

/* *** epv structures ***

static PortableServer_ServantBase__epv impl_Calculator_base_epv = {
    NULL, /* _private data */
    (gpointer) & impl_Calculator_fini, /* finalize routine */
    NULL, /* default_POA routine */
};
static POA_Calculator__epv impl_Calculator_epv = {
    NULL, /* _private */
    (gpointer) & impl_Calculator_add,
    (gpointer) & impl_Calculator_sub,
};

/* *** vepv structures ***

static POA_Calculator__vepv impl_Calculator_vepv = {
    &impl_Calculator_base_epv,
    &impl_Calculator_epv,
};

/* *** Stub implementations ***

static Calculator
impl_Calculator__create (PortableServer_POA poa, CORBA_Environment * ev)
{
    Calculator retval;
    impl_POA_Calculator *newservant;
    PortableServer_ObjectId *objid;

    newservant = g_new0(impl_POA_Calculator, 1);
    newservant->servant.vepv = &impl_Calculator_vepv;
    newservant->poa =

```

```

    (PortableServer_POA) CORBA_Object_duplicate((CORBA_Object) poa, ev);
POA_Calculator__init((PortableServer_Servant) newservant, ev);
/* Before servant is going to be activated all
 * private attributes must be initialized. */

/* ----- init private attributes here ----- */
/* ----- ----- end ----- */

objid = PortableServer_POA_activate_object(poa, newservant, ev);
CORBA_free(objid);
retval = PortableServer_POA_servant_to_reference(poa, newservant, ev);

return retval;
}

/***
* impl_Calculator__fini
*
* Destructor called after servant has been deactivated finally.
* In case any operation invocation, method invocation is being delayed.
* Note, in former versions of ORBIT2 this function would have been
* named impl_Calculator__destroy.
*/
static void
impl_Calculator__fini (impl_POA_Calculator * servant,
                      CORBA_Environment * ev)
{
    CORBA_Object_release((CORBA_Object) servant->poa, ev);

    /* No further remote method calls are delegated to
     * servant and you may free your private attributes. */
    /* ----- free private attributes here ----- */
    /* ----- ----- end ----- */

    POA_Calculator__fini((PortableServer_Servant) servant, ev);

    g_free (servant);
}

static CORBA_double
impl_Calculator_add(impl_POA_Calculator * servant,
                    const CORBA_double number1,
                    const CORBA_double number2, CORBA_Environment * ev)
{
    CORBA_double retval;

    /* ----- insert method code here ----- */
    g_print ("%f + %f\n", number1, number2);
    retval = number1 + number2;
    /* ----- ----- end ----- */

    return retval;
}

static CORBA_double
impl_Calculator_sub(impl_POA_Calculator * servant,
                    const CORBA_double number1,

```

```

    const CORBA_double number2, CORBA_Environment * ev)
{
    CORBA_double retval;

    /* ----- insert method code here ----- */
    g_print ("%f - %f\n", number1, number2);
    retval = number1 - number2;
    /* ----- ----- end ----- */

    return retval;
}

```

5.10.2. Compiling client & server

Example 5-48. Makefile

```

PREFIX ?= /usr
CC = gcc
TARGETS=calculator-client mt-calculator-server
ORBIT_IDL=$(PREFIX)/bin/orbit-idl-2
CFLAGS=-DORBIT2=1 -D_REENTRANT -I$(PREFIX)/include/orbit-2.0 \
-I$(PREFIX)/include/linc-1.0 -I$(PREFIX)/include/glib-2.0 \
-I$(PREFIX)/lib/glib-2.0/include -g
LDFLAGS= -Wl,--export-dynamic -L$(PREFIX)/lib -lORBit-2 -llinc -lgmodule-2.0 \
-lidl -lgobject-2.0 -lgthread-2.0 -lpthread -lglib-2.0 -lm \
-lORBitCosNaming-2

IDLOUT=calculator-common.c calculator-stubs.c calculator-skels.c calculator.h

all: $(IDLOUT) calculator-client mt-calculator-server

mt-calculator-server.o : mt-calculator-server.c calculator-skelimpl.c

calculator-client : calculator-client.o calculator-stubs.o calculator-common.o examples-toolkit.o
mt-calculator-server : mt-calculator-server.o calculator-skels.o calculator-common.o examples-too

$(IDLOUT): calculator.idl
$(ORBIT_IDL) --skeleton-impl $^

%-skelimpl.c: %.idl
$(ORBIT_IDL) --skeleton-impl $^

clean:
rm -rf *.o *~ $(IDLOUT) *.ior *.ref

distclean: clean
rm -rf calculator-client mt-calculator-server

```

Chapter 6. How to do garbage collection under CORBA

I wanted to do garbage collection under CORBA, and so I asked some questions on the ORBit list. Here is a distillation of the answers which I received, mostly verbatim and not necessarily in order.

Editor's note - this chapter came from Todd Lewis

6.1. The question

I asked the following question on the ORBit list:

"As a client, when I no longer need an object, how do I properly release it? I see a couple of different candidate functions, but I'm not sure which one is proper. If there's a piece of example code which I've overlooked, then a simple pointer thereto would suffice. My copy of the Henning & Vinoski book is on the way, and so hopefully I won't be so clueless here soon... "

6.2. Difference between the client and the server

Elliot Lee, ever the prescient one, asked:

"Object or object reference? "

And then observed:

"I think Todd is confused as to what the difference between object references and objects is. Think of an object reference and an object as being analogous to a pointer and pointed-to memory, respectively. You can stop using a pointer, but until you get the server side to actually free() the memory (object) being pointed to (referenced), it is still there. "

Indeed I was confused. There are actually two processes which occur within CORBA:

- the client drops all references to an object, after which the ORB local to the client then can clean up all of its data structures related to that object, and
- the server can decide that the object needs to be destroyed, and it then does the job of deactivating the object (so that the POA can know not to answer any more queries to that object) and freeing associated resources, etc.

Since object references can be generated in one program, passed to a second program, the first program can forget about it, and the second can continue, these are separate processes. It was understanding this fact which was the biggest impediment to my figuring this matter out.

Sascha Brawer <brawer@coli.uni-sb.de> described these two potential interpretations of what I wanted to do, reflecting a nuance which I did not appreciate when I asked the question:

- You want the client to forget about the object reference, but the server-side object should continue its life: Call CORBA_free on the client side. The purpose of CORBA_free is to release the memory in the client. Therefore, the server will not get any notification about this. If other clients had references to the same object, they will continue to work.
- You want to destroy the object on the server: define a method in the object's interface, e.g. "destroy" (though any name is fine). First, call that method on the client side. The server will receive the call, and your server implementation will destroy the object. Second, call CORBA_free on the client side, to free the client-side memory for the object reference which has now become stale. If other clients had references to the same object, they will receive an exception as soon they call a method on that object. However, they won't be notified in advance, because the server does not keep track on issued references.

Which Elliot Lee then corrected with:

CORBA_Object_release() on object references, CORBA_free() on data structures.

Dick Porter added:

It is only the client side. These pseudo-object methods do not cause requests to be made to the server.

6.3. Server-side deactivation

Ok, so CORBA_Object_release takes care of the client side. This isn't enough, because, as Elliot Lee pointed out, to state the point slightly differently:

On Tue, 20 Apr 1999, Svanberg Liss wrote:
> Btw, what does CORBA_Object_duplicate & CORBA_Object_release do
> server?

Nothing..

So, what do you do on the server side? Elliot answered this, too:

> and... hmm, what kind of call does destroy the object in the server
when
> release doesn't?

You PortableServer_POA_deactivate_object(poa, objid) to tell the POA not to take any more requests for the specified objid.

Let's take a look at what this means in terms of actual code. If you run **orbit-idl --skeleton_impl foo.idl** on your idl file, you will get a file foo-impl.c. Inside of that file, you will see functions like the following:

```
/* You shouldn't call this routine directly without first deactivating
```

```

the servant... */

static void

impl_CosTransactions_Control__destroy(
    impl_POA_CosTransactions_Control * servant,
    CORBA_Environment * ev)

{
    POA_CosTransactions_Control__fini((PortableServer_Servant) servant,
    ev);

    g_free(servant);
}

```

Where it says "You shouldn't call this routine directly without first deactivating the servant...", it means that you should call PortableServer_POA_deactivate_object() on the servant first.

FIXME: I don't understand what POA_CosTransactions_Control__fini does here; how is it different from PortableServer_POA_deactivate_object? Anyway, this is the final step you take after your object is deactivated; you can then free the POA servant struct which you created in your factory (or wherever.)

6.4. Why is this an issue?

Sascha Brawer suggests: Maybe the confusion arises because there do exist distributed object systems that perform this sort of reference counting, allowing the server to know when no client has a reference left. DCOM has such a mechanism, and ILU has something similar, AFAIK.

Why doesn't CORBA follow these other systems? My personal impression is that this is another case of CORBA doing the right thing instead of the easy thing. Sascha continues:

However, I've read somewhere (don't remember the exact location, sorry...) that the problem with distributed reference counting would be that first, it consumes network bandwidth, and second, it does not work well with unreliable network connections. It was told in that article that these drawbacks would have been the rationale for designing CORBA without refcounting.

This is a problem. If your client disappears, then you've got unneeded objects lying around. All it takes for clients to disappear is for them to be coded by bad programmers, and we all know how unlikely that is, right? So how does one deal with this? There are several ways. The easiest is to have a timeout. This is the approach that I am using in the GNU Transaction Server; when the timeout expires, I deactivate all of my servant objects and free up their resources. Fortunately, the CosTransactions spec supports timeouts on transactions. Unfortunately, I don't really see how to do timeouts with the normal CORBA event model, so I'm going to have to use the ORBit-specific hack of having a glib event loop which supports both CORBA events and timeouts. Another way, I am told, is something called an Evictor pattern. I should understand this soon once I get my fancy CORBA book in the mail. The final way is just to leak memory like a sieve leaks goldfish; this is the easiest thing to do.